
hvac

Release 0.10.0

Apr 01, 2020

Contents

1	hvac	1
1.1	Installation	2
1.2	Getting Started	2
1.2.1	Initialize the Client	2
1.2.2	Vault Cluster - Initialize and Seal/Unseal	2
1.2.3	Read and write to secrets engines	3
1.2.4	Authentication	4
2	Usage	5
2.1	Secrets Engines	5
2.1.1	AWS	5
2.1.2	Azure	8
2.1.3	GCP	10
2.1.4	Identity	16
2.1.5	PKI	26
2.1.6	KV Secrets Engines	32
2.1.7	Transit	39
2.2	Auth Methods	56
2.2.1	Approle	56
2.2.2	AWS	56
2.2.3	Azure	62
2.2.4	GCP	65
2.2.5	GitHub	69
2.2.6	Kubernetes	71
2.2.7	LDAP	71
2.2.8	MFA	75
2.2.9	Okta	77
2.2.10	Token	80
2.2.11	Authenticate to different auth backends	81
2.3	System Backend	82
2.3.1	Audit	82
2.3.2	Auth	85
2.3.3	Health	89
2.3.4	Init	90
2.3.5	Key	92
2.3.6	Leader	99

2.3.7	Lease	100
2.3.8	Mount	104
2.3.9	Namespace	109
2.3.10	Policy	110
2.3.11	Seal	114
2.3.12	Wrapping	117
2.4	Initialize and seal/unseal	118
3	Advanced Usage	119
3.1	Making Use of Private CA	119
3.2	Custom Requests / HTTP Adapter	120
3.3	Vault Agent Unix Socket Listener	120
4	Source Reference	123
4.1	hvac.v1	123
4.2	hvac.api	166
4.3	hvac.api.auth_methods	168
4.4	hvac.api.secrets_engines	200
4.5	hvac.api.system_backend	247
4.6	hvac.utils	263
4.7	hvac.aws_utils	266
4.8	hvac.adapters	266
4.9	hvac.exceptions	271
5	Contributing	273
5.1	Typical Develo‍pment Environment Setup	273
5.2	Testing	273
5.3	Updating Requirements	274
5.4	Documentation	274
5.4.1	Adding New Documentation Files	274
5.4.2	Testing Docs	274
5.4.3	Examples	274
5.5	Backwards Compatibility Breaking Changes	274
5.6	Creating / Publishing Releases	275
6	Changelog	277
6.1	0.10.0 (February 26th, 2020)	277
6.1.1	Features	277
6.1.2	Documentation	277
6.1.3	Miscellaneous	277
6.2	0.9.6 (November 20th, 2019)	279
6.2.1	Features	279
6.2.2	Documentation	279
6.2.3	Miscellaneous	279
6.3	0.9.5 (July 19th, 2019)	279
6.3.1	Features	279
6.3.2	Documentation	280
6.4	0.9.4 (July 18th, 2019)	280
6.4.1	Features	280
6.4.2	Bug Fixes	280
6.4.3	Documentation	280
6.4.4	Miscellaneous	280
6.5	0.9.3 (July 7th, 2019)	280
6.5.1	Features	280
6.5.2	Bug Fixes	280

6.5.3	Documentation	280
6.5.4	Miscellaneous	281
6.6	0.9.2 (June 8th, 2019)	281
6.7	0.9.1 (May 25th, 2019)	281
6.8	0.9.0 (May 23rd, 2019)	282
6.9	0.8.2 (April 4th, 2019)	282
6.10	0.8.1 (March 31st, 2019)	282
6.11	0.8.0 (March 29th, 2019)	282
6.12	0.7.2 (January 1st, 2019)	283
6.13	0.7.1 (December 19th, 2018)	283
6.14	0.7.0 (November 1st, 2018)	284
6.15	0.6.4 (September 5th, 2018)	284
6.16	0.6.3 (August 8th, 2018)	284
6.17	0.6.2 (July 19th, 2018)	285
6.18	0.6.1 (July 5th, 2018)	286
6.19	0.6.0 (June 14, 2018)	286
6.20	0.5.0 (February 20, 2018)	287
6.21	0.4.0 (February 1, 2018)	287
6.22	0.3.0 (November 9, 2017)	287
6.23	0.2.17 (December 15, 2016)	287
6.24	0.2.16 (September 12, 2016)	288
6.25	0.2.15 (June 22nd, 2016)	288
6.26	0.2.14 (June 2nd, 2016)	288
6.27	0.2.13 (May 31st, 2016)	288
6.28	0.2.12 (May 12th, 2016)	289
6.29	0.2.10 (April 8th, 2016)	289
6.30	0.2.9 (March 18th, 2016)	289
6.31	0.2.8 (February 2nd, 2016)	289
6.32	0.2.7 (December 16th, 2015)	289
6.33	0.2.6 (October 30th, 2015)	289
6.34	0.2.5 (September 29th, 2015)	290
6.35	0.2.4 (July 23rd, 2015)	290
6.36	0.2.3 (July 18th, 2015)	290
6.37	0.2.2 (June 12th, 2015)	290
6.38	0.2.1 (June 3rd, 2015)	290
6.39	0.2.0 (May 25th, 2015)	290
6.40	0.1.1 (May 20th, 2015)	291
6.41	0.1.0 (May 17th, 2015)	291
7	Indices and tables	293
	Python Module Index	295
	Index	297



HashiCorp Vault API client for Python 2.7/3.x

chat on gitter

Tested against the latest release, HEAD ref, and 3 previous minor versions (counting back from the latest release) of Vault. Current official support covers Vault v1.0.3 or later.

1.1 Installation

```
pip install hvac
```

If you would like to be able to return parsed HCL data as a Python dict for methods that support it:

```
pip install "hvac[parser]"
```

1.2 Getting Started

1.2.1 Initialize the Client

Using TLS:

```
>>> client = hvac.Client(url='https://localhost:8200')
>>> client.is_authenticated()
True
```

Using TLS with client-side certificate authentication:

```
>>> client = hvac.Client(
...     url='https://localhost:8200',
...     token=os.environ['VAULT_TOKEN'],
...     cert=(client_cert_path, client_key_path),
...     verify=server_cert_path,
... )
>>> client.is_authenticated()
True
```

Using Vault Enterprise namespace:

```
>>> client = hvac.Client(
...     url='https://localhost:8200',
...     namespace=os.getenv('VAULT_NAMESPACE'),
... )
```

Using plaintext / HTTP (not recommended for anything other than development work):

```
>>> client = hvac.Client(url='http://localhost:8200')
```

1.2.2 Vault Cluster - Initialize and Seal/Unseal

```
>>> client.sys.is_initialized()
False

>>> shares = 5
>>> threshold = 3
>>> result = client.sys.initialize(shares, threshold)
>>> root_token = result['root_token']
>>> keys = result['keys']
>>> client.sys.is_initialized()
```

(continues on next page)

(continued from previous page)

```

True
>>> client.token = root_token

>>> client.sys.is_sealed()
True
>>> # Unseal a Vault cluster with individual keys
>>> unseal_response1 = client.sys.submit_unseal_key(keys[0])
>>> unseal_response2 = client.sys.submit_unseal_key(keys[1])
>>> unseal_response3 = client.sys.submit_unseal_key(keys[2])
>>> client.sys.is_sealed()
False
>>> # Seal a previously unsealed Vault cluster.
>>> client.sys.seal()
<Response [204]>
>>> client.sys.is_sealed()
True

>>> # Unseal with multiple keys until threshold met
>>> unseal_response = client.sys.submit_unseal_keys(keys)

>>> client.sys.is_sealed()
False

```

1.2.3 Read and write to secrets engines

Note: Vault currently defaults the `secret/` path to the KV secrets engine *version 2* automatically when the Vault server is started in “dev” mode.

Note: Starting with Vault v1.1.0, `_no_` KV secrets engine is mounted by default. I.e., outside of dev mode, a KV engine mounted under path `secret/` must be explicitly enabled before use.

KV Secrets Engine - Version 2

```

>>> # Retrieve an authenticated hvac.Client() instance
>>> client = test_utils.create_client()
>>>
>>> # Write a k/v pair under path: secret/foo
>>> create_response = client.secrets.kv.v2.create_or_update_secret(
...     path='foo',
...     secret=dict(baz='bar'),
... )
>>>
>>> # Read the data written under path: secret/foo
>>> read_response = client.secrets.kv.read_secret_version(path='foo')
>>> print('Value under path "secret/foo" / key "baz": {val}'.format(
...     val=read_response['data']['data']['baz'],
... ))
Value under path "secret/foo" / key "baz": bar

```

(continues on next page)

(continued from previous page)

```
>>>
>>> # Delete all metadata/versions for path: secret/foo
>>> client.secrets.kv.delete_metadata_and_all_versions('foo')
<Response [204]>
```

KV Secrets Engine - Version 1

Preferred usage:

```
>>> create_response = client.secrets.kv.v1.create_or_update_secret('foo',
↳secret=dict(baz='bar'))
>>> read_response = client.secrets.kv.v1.read_secret('foo')
>>> print('Value under path "secret/foo" / key "baz": {val}'.format(
...     val=read_response['data']['baz'],
... ))
Value under path "secret/foo" / key "baz": bar
>>> delete_response = client.secrets.kv.v1.delete_secret('foo')
```

1.2.4 Authentication

Basic Token Authentication

```
# Token
>>> client.token = os.environ['VAULT_TOKEN']
>>> client.is_authenticated()
True
```

LDAP Authentication Example

```
>>> client = hvac.Client(url='https://localhost:8200')
>>> # LDAP, getpass -> user/password, bring in LDAP3 here for teststup?
>>> login_response = client.auth.ldap.login(
...     username=os.environ['LDAP_USERNAME'],
...     password=os.environ['LDAP_PASSWORD'],
... )
>>> client.is_authenticated()
True
>>> print('The client token returned from the LDAP auth method is: {token}'.format(
...     token=login_response['auth']['client_token']
... ))
The client token returned from the LDAP auth method is: ...
```

2.1 Secrets Engines

2.1.1 AWS

Contents

- AWS
 - *Configure Root IAM Credentials*
 - *Rotate Root IAM Credentials*
 - *Configure Lease*
 - *Read Lease*
 - *Create or Update Role*
 - * *Legacy Parameters*
 - *Read Role*
 - *List Roles*
 - *Delete Role*
 - *Generate Credentials*

Configure Root IAM Credentials

Source reference: `hvac.api.secrets_engines.Aws.configure_root_iam_credentials()`

```
import os

import hvac
client = hvac.Client()

client.secrets.aws.configure_root_iam_credentials(
    access_key=os.getenv('AWS_ACCESS_KEY_ID'),
    secret_key=os.getenv('AWS_SECRET_ACCESS_KEY'),
)
```

Rotate Root IAM Credentials

Source reference: `hvac.api.secrets_engines.Aws.rotate_root_iam_credentials()`

```
import hvac

client = hvac.Client()

client.secrets.aws.rotate_root_iam_credentials()
```

Configure Lease

Source reference: `hvac.api.secrets_engines.Aws.configure_lease()`

```
import hvac

client = hvac.Client()

# Set the default least TTL to 300 seconds / 5 minutes
client.secrets.aws.configure_lease(
    lease='300s',
)
```

Read Lease

Source reference: `hvac.api.secrets_engines.Aws.read_lease()`

```
import hvac

client = hvac.Client()

read_lease_response = client.secrets.aws.read_lease()
print('The current "lease_max" TTL is: {lease_max}'.format(
    lease_max=read_lease_response['data']['lease_max'],
))
```

Create or Update Role

Source reference: `hvac.api.secrets_engines.Aws.create_or_update_role()`

```
import hvac

client = hvac.Client()

describe_ec2_policy_doc = {
```

(continues on next page)

(continued from previous page)

```

    'Version': '2012-10-17',
    'Statement': [
        {
            'Resource': '*'
            'Action': 'ec2:Describe*',
            'Effect': 'Allow',
        },
    ],
}
client.secrets.aws.create_or_update_role(
    name='hvac-role',
    credential_type='assumed_role',
    policy_document=describe_ec2_policy_doc,
    policy_arns=['arn:aws:iam::aws:policy/AmazonVPCReadOnlyAccess'],
)

```

Legacy Parameters

Note: In previous versions of Vault (before version 0.11.0), this API route only supports the *policy_document* and *policy_arns* parameters (which hvac will translate to *policy* and *arn* parameters respectively in the request sent to Vault). If running these versions of Vault, the *legacy_params* parameter on this method can be set to *True*.

For older versions of Vault (any version before 0.11.0):

```

import hvac
client = hvac.Client()

describe_ec2_policy_doc = {
    'Version': '2012-10-17',
    'Statement': [
        {
            'Resource': '*'
            'Action': 'ec2:Describe*',
            'Effect': 'Allow',
        },
    ],
}

# Note: with the legacy params, the `policy_arns` parameter is translated to `arn`
# in the request sent to Vault and only one ARN is accepted. If a list is provided,
# hvac will only use the first ARN in the list.
client.secrets.aws.create_or_update_role(
    name='hvac-role',
    credential_type='assumed_role',
    policy_document=describe_ec2_policy_doc,
    policy_arns='arn:aws:iam::aws:policy/AmazonVPCReadOnlyAccess',
    legacy_params=True,
)

```

Read Role

Source reference: `hvac.api.secrets_engines.Aws.read_role()`

```
import hvac
client = hvac.Client()

read_role_response = client.secrets.aws.read_role(
    name='hvac-role',
)
print('The credential type for role "hvac-role" is: {cred_type}'.format(
    cred_type=read_role_response['data']['credential_types'],
))
```

List Roles

Source reference: *hvac.api.secrets_engines.Aws.list_roles()*

```
import hvac
client = hvac.Client()

list_roles_response = client.secrets.aws.list_roles()
print('AWS secrets engine role listing: {roles}'.format(
    roles=', '.join(list_roles_response['data']['keys'])
))
```

Delete Role

Source reference: *hvac.api.secrets_engines.Aws.delete_role()*

```
import hvac
client = hvac.Client()

client.secrets.aws.delete_role(
    name='hvac-role',
)
```

Generate Credentials

Source reference: *hvac.api.secrets_engines.Aws.generate_credentials()*

```
import hvac
client = hvac.Client()

gen_creds_response = client.secrets.aws.generate_credentials(
    name='hvac-role',
)
print('Generated access / secret keys: {access} / {secret}'.format(
    access=gen_creds_response['data']['access_key'],
    secret=gen_creds_response['data']['secret_key'],
))
```

2.1.2 Azure

Note: Every method under the `Azure` class includes a `mount_point` parameter that can be used to address the Azure secret engine under a custom mount path. E.g., If enabling the Azure secret engine using Vault’s CLI commands via `vault secrets enable -path=my-azure azure`, the `mount_point` parameter in `hvac.api.secrets_engines.Azure()` methods would need to be set to “my-azure”.

Configure

`hvac.api.secrets_engines.Azure.configure()`

```
import hvac
client = hvac.Client()

client.secrets.azure.configure(
    subscription_id='my-subscription-id',
    tenant_id='my-tenant-id',
)
```

Read Config

`hvac.api.secrets_engines.Azure.read_config()`

```
import hvac
client = hvac.Client()

azure_secret_config = client.secrets.azure.read_config()
print('The Azure secret engine is configured with a subscription ID of {id}'.format(
    id=azure_secret_config['subscription_id'],
))
```

Delete Config

`hvac.api.secrets_engines.Azure.delete_config()`

```
import hvac
client = hvac.Client()

client.secrets.azure.delete_config()
```

Create Or Update A Role

`hvac.api.secrets_engines.Azure.create_or_update_role()`

```
import hvac
client = hvac.Client()

azure_roles = [
    {
        'role_name': "Contributor",
        'scope': "/subscriptions/95e675fa-307a-455e-8cdf-0a66aeaa35ae",
```

(continues on next page)

(continued from previous page)

```
    },  
  ]  
  client.secrets.azure.create_or_update_role(  
    name='my-azure-secret-role',  
    azure_roles=azure_roles,  
  )
```

List Roles

hvac.api.secrets_engines.Azure.list_roles()

```
import hvac  
client = hvac.Client()  
  
azure_secret_engine_roles = client.secrets.azure.list_roles()  
print('The following Azure secret roles are configured: {roles}'.format(  
    roles=', '.join(roles['keys']),  
))
```

Generate Credentials

hvac.api.secrets_engines.Azure.generate_credentials()

```
import hvac  
from azure.common.credentials import ServicePrincipalCredentials  
  
client = hvac.Client()  
azure_creds = client.secrets.azure.secret.generate_credentials(  
    name='some-azure-role-name',  
)  
azure_spc = ServicePrincipalCredentials(  
    client_id=azure_creds['client_id'],  
    secret=azure_creds['client_secret'],  
    tenant=TENANT_ID,  
)
```

2.1.3 GCP

- *Configure*
- *Read Config*
- *Create Or Update Roleset*
- *Rotate Roleset Account*
- *Rotate Roleset Account Key*
- *Read Roleset*
- *List Rolesets*
- *Delete Roleset*

- *Generate OAuth2 Access Token*
- *Generate Service Account Key*

Configure

`Gcp.configure` (*credentials=None, ttl=None, max_ttl=None, mount_point='gcp'*)
Configure shared information for the Gcp secrets engine.

Supported methods: POST: `/{{mount_point}}/config`. Produces: 204 (empty body)

Parameters

- **credentials** (*str | unicode*) – JSON credentials (either file contents or '@path/to/file') See docs for alternative ways to pass in to this parameter, as well as the required permissions.
- **ttl** (*int | str*) – Specifies default config TTL for long-lived credentials (i.e. service account keys). Accepts integer number of seconds or Go duration format string.
- **max_ttl** (*int | str*) – Specifies the maximum config TTL for long-lived credentials (i.e. service account keys). Accepts integer number of seconds or Go duration format string.**
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

credentials = test_utils.load_config_file('example.jwt.json')
configure_response = client.secrets.gcp.configure(
    credentials=credentials,
    max_ttl=3600,
)
print(configure_response)
```

Example output:

```
<Response [204]>
```

Read Config

`Gcp.read_config` (*mount_point='gcp'*)
Read the configured shared information for the Gcp secrets engine.

Credentials will be omitted from returned data.

Supported methods: GET: `/{{mount_point}}/config`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

read_config_response = client.secrets.gcp.read_config()
print('Max TTL for GCP secrets engine set to: {max_ttl}'.format(max_ttl=read_config_
↳response['data']['max_ttl']))
```

Example output:

```
Max TTL for GCP secrets engine set to: 3600
```

Create Or Update Roleset

Gcp.**create_or_update_roleset** (*name, project, bindings, secret_type=None, token_scopes=None, mount_point='gcp'*)

Create a roleset or update an existing roleset.

See roleset docs for the GCP secrets backend to learn more about what happens when you create or update a roleset.

Supported methods: POST: `/mount_point/roleset/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role. Cannot be updated.
- **project** (*str | unicode*) – Name of the GCP project that this roleset’s service account will belong to. Cannot be updated.
- **bindings** (*str | unicode*) – Bindings configuration string (expects HCL or JSON format in raw or base64-encoded string)
- **secret_type** (*str | unicode*) – Cannot be updated.
- **token_scopes** (*list[str]*) – List of OAuth scopes to assign to access_token secrets generated under this role set (access_token role sets only)
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```

import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

bindings = """
    resource "//cloudresourcemanager.googleapis.com/project/some-gcp-project-id" {
        roles = [
            "roles/viewer"
        ],
    }
"""
token_scopes = [
    'https://www.googleapis.com/auth/cloud-platform',
    'https://www.googleapis.com/auth/bigquery',
]

roleset_response = client.secrets.gcp.create_or_update_roleset(
    name='hvac-doctest',
    project='some-gcp-project-id',
    bindings=bindings,
    token_scopes=token_scopes,
)

```

Rotate Roleset Account

Gcp.**rotate_roleset_account** (*name*, *mount_point='gcp'*)

Rotate the service account this roleset uses to generate secrets.

This also replaces the key access_token roleset. This can be used to invalidate old secrets generated by the roleset or fix issues if a roleset's service account (and/or keys) was changed outside of Vault (i.e. through GCP APIs/cloud console).

Supported methods: POST: /{mount_point}/roleset/{name}/rotate. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Name of the role.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```

import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

rotate_response = client.secrets.gcp.rotate_roleset_account(name='hvac-doctest')

```

Rotate Roleset Account Key

Gcp.**rotate_roleset_account_key** (*name*, *mount_point='gcp'*)

Rotate the service account key this roleset uses to generate access tokens.

This does not recreate the roleset service account.

Supported methods: POST: `/{{mount_point}}/roleset/{name}/rotate-key`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

rotate_response = client.secrets.gcp.rotate_roleset_account_key(name='hvac-doctest')
```

Read Roleset

`Gcp.read_roleset` (*name, mount_point='gcp'*)

Read a roleset.

Supported methods: GET: `/{{mount_point}}/roleset/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `dict`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

read_response = client.secrets.gcp.read_roleset(name='hvac-doctest')
```

List Rolesets

`Gcp.list_rolesets` (*mount_point='gcp'*)

List configured rolesets.

Supported methods: LIST: `/{{mount_point}}/rolesets`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

list_response = client.secrets.gcp.list_rolesets()
```

Delete Roleset

`Gcp.delete_roleset` (*name*, *mount_point='gcp'*)

Delete an existing roleset by the given name.

Supported methods: DELETE: `/{mount_point}/roleset/{name}` Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Name of the role.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

delete_response = client.secrets.gcp.delete_roleset(name='hvac-doctest')
```

Generate OAuth2 Access Token

`Gcp.generate_oauth2_access_token` (*roleaset*, *mount_point='gcp'*)

Generate an OAuth2 token with the scopes defined on the roleaset.

This OAuth access token can be used in GCP API calls, e.g. `curl -H "Authorization: Bearer $TOKEN" ...`

Supported methods: GET: `/{mount_point}/token/{roleaset}`. Produces: 200 application/json

Parameters

- **roleaset** (*str* | *unicode*) – Name of an roleaset with secret type `access_token` to generate `access_token` under.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

token_response = client.secrets.gcp.generate_oauth2_access_token(roleset='hvac-doctest
→')
```

Generate Service Account Key

```
Gcp.generate_service_account_key(roleset, key_algorithm='KEY_ALG_RSA_2048',
key_type='TYPE_GOOGLE_CREDENTIALS_FILE',
method='POST', mount_point='gcp')
```

Generate Secret (IAM Service Account Creds): Service Account Key

If using GET ('read'), the optional parameters will be set to their defaults. Use POST if you want to specify different values for these params.

Parameters

- **roleset** (*str* | *unicode*) – Name of an roleset with secret type `service_account_key` to generate key under.
- **key_algorithm** (*str* | *unicode*) – Key algorithm used to generate key. Defaults to 2k RSA key You probably should not choose other values (i.e. 1k),
- **key_type** (*str* | *unicode*) – Private key type to generate. Defaults to JSON credentials file.
- **method** (*str* | *unicode*) – Supported methods: POST: `/mount_point/key/{roleset}`. Produces: 200 application/json GET: `/mount_point/key/{roleset}`. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

key_response = client.secrets.gcp.generate_service_account_key(roleset='hvac-doctest')
```

2.1.4 Identity

New in version Vault: 0.9.0

Contents

- *Identity*

- *Entity*
 - * *Create Or Update Entity*
 - * *Create Or Update Entity By Name*
 - * *Read Entity*
 - * *Read Entity By Name*
 - * *Update Entity*
 - * *Delete Entity*
 - * *Delete Entity By Name*
 - * *List Entities*
 - * *List Entities By Name*
 - * *Merge Entities*
- *Entity Alias*
 - * *Create Or Update Entity Alias*
 - * *Read Entity Alias*
 - * *Update Entity Alias*
 - * *List Entity Aliases*
 - * *Delete Entity Alias*
- *Group*
 - * *Create Or Update Group*
 - * *Read Group*
 - * *Update Group*
 - * *Delete Group*
 - * *List Groups*
 - * *List Groups By Name*
 - * *Create Or Update Group By Name*
 - * *Read Group By Name*
 - * *Delete Group By Name*
- *Group Alias*
 - * *Create Or Update Group Alias*
 - * *Update Group Alias*
 - * *Read Group Alias*
 - * *Delete Group Alias*
 - * *List Group Aliases*
- *Lookup*
 - * *Lookup Entity*

* *Lookup Group*

Entity

Create Or Update Entity

hvac.api.secrets_engines.Identity.create_or_update_entity()

```
import hvac
client = hvac.Client()

create_response = client.secrets.identity.create_or_update_entity(
    name='hvac-entity',
    metadata=dict(extra_datas='yup'),
)
entity_id = create_response['data']['id']
print('Entity ID for "hvac-entity" is: {id}'.format(id=entity_id))
```

Create Or Update Entity By Name

hvac.api.secrets_engines.Identity.create_or_update_entity_by_name()

```
import hvac
client = hvac.Client()

client.secrets.identity.create_or_update_entity_by_name(
    name='hvac-entity',
    metadata=dict(new_datas='uhuh'),
)
```

Read Entity

hvac.api.secrets_engines.Identity.read_entity()

```
import hvac
client = hvac.Client()

read_response = client.secrets.identity.read_entity(
    entity_id=entity_id,
)
name = read_response['data']['name']
print('Name for entity ID {id} is: {name}'.format(id=entity_id, name=name))
```

Read Entity By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.read_entity_by_name()


```

import hvac
client = hvac.Client()

read_response = client.secrets.identity.read_entity_by_name(
    name='hvac-entity',
)
entity_id = read_response['data']['id']
print('Entity ID for "hvac-entity" is: {id}'.format(id=entity_id))

```

Update Entity

hvac.api.secrets_engines.Identity.update_entity()

```

import hvac
client = hvac.Client()

client.secrets.identity.update_entity(
    entity_id=entity_id,
    metadata=dict(new_metadata='yup'),
)

```

Delete Entity

hvac.api.secrets_engines.Identity.delete_entity()

```

import hvac
client = hvac.Client()

client.secrets.identity.delete_entity(
    entity_id=entity_id,
)

```

Delete Entity By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.delete_entity_by_name()

```

import hvac
client = hvac.Client()

client.secrets.identity.delete_entity_by_name(
    name='hvac-entity',
)

```

List Entities

hvac.api.secrets_engines.Identity.list_entities()

```
import hvac
client = hvac.Client()

list_response = client.secrets.identity.list_entities()
entity_keys = list_response['data']['keys']
print('The following entity IDs are currently configured: {keys}'.format(keys=entity_
↪keys))
```

List Entities By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.list_entities_by_name()

```
import hvac
client = hvac.Client()

list_response = client.secrets.identity.list_entities_by_name()
entity_keys = list_response['data']['keys']
print('The following entity names are currently configured: {keys}'.
↪format(keys=entity_keys))
```

Merge Entities

hvac.api.secrets_engines.Identity.merge_entities()

```
import hvac
client = hvac.Client()

client.secrets.identity.merge_entities(
    from_entity_ids=from_entity_ids,
    to_entity_id=to_entity_id,
)
```

Entity Alias

Create Or Update Entity Alias

hvac.api.secrets_engines.Identity.create_or_update_entity_alias()

```
import hvac
client = hvac.Client()

create_response = client.secrets.identity.create_or_update_entity_alias(
    name='hvac-entity-alias',
    canonical_id=entity_id,
    mount_accessor='auth_approle_73c16de3',
)
alias_id = create_response['data']['id']
print('Alias ID for "hvac-entity-alias" is: {id}'.format(id=alias_id))
```

Read Entity Alias

hvac.api.secrets_engines.Identity.read_entity_alias()

```
import hvac
client = hvac.Client()

read_response = client.secrets.identity.read_entity_alias(
    alias_id=alias_id,
)
name = read_response['data']['name']
print('Name for entity alias {id} is: {name}'.format(id=alias_id, name=name))
```

Update Entity Alias

hvac.api.secrets_engines.Identity.update_entity_alias()

```
import hvac
client = hvac.Client()

client.secrets.identity.update_entity_alias(
    alias_id=alias_id,
    name='new-alias-name',
    canonical_id=entity_id,
    mount_accessor='auth_approle_73c16de3',
)
```

List Entity Aliases

hvac.api.secrets_engines.Identity.list_entity_aliases()

```
import hvac
client = hvac.Client()

list_response = client.secrets.identity.list_entity_aliases()
alias_keys = list_response['data']['keys']
print('The following entity alias IDs are currently configured: {keys}'.
      ↪format(keys=alias_keys))
```

Delete Entity Alias

hvac.api.secrets_engines.Identity.delete_entity_alias()

```
import hvac
client = hvac.Client()

client.secrets.identity.delete_entity_alias(
    alias_id=alias_id,
)
```

Group

Create Or Update Group

hvac.api.secrets_engines.Identity.create_or_update_group()

```
import hvac
client = hvac.Client()

create_response = client.secrets.identity.create_or_update_group(
    name='hvac-group',
    metadata=dict(extra_datas='we gots em'),
)
group_id = create_response['data']['id']
print('Group ID for "hvac-group" is: {id}'.format(id=group_id))
```

Read Group

hvac.api.secrets_engines.Identity.read_group()

```
import hvac
client = hvac.Client()

read_response = client.secrets.identity.read_group(
    group_id=group_id,
)
name = read_response['data']['name']
print('Name for group ID {id} is: {name}'.format(id=group_id, name=name))
```

Update Group

hvac.api.secrets_engines.Identity.update_group()

```
import hvac
client = hvac.Client()

client.secrets.identity.update_group(
    group_id=group_id,
    metadata=dict(new_metadata='yup'),
)
```

Delete Group

hvac.api.secrets_engines.Identity.delete_group()

```
import hvac
client = hvac.Client()

client.secrets.identity.delete_group(
    group_id=group_id,
)
```

List Groups

hvac.api.secrets_engines.Identity.list_groups()

```
import hvac
client = hvac.Client()

list_response = client.secrets.identity.list_groups()
group_keys = list_response['data']['keys']
print('The following group IDs are currently configured: {keys}'.format(keys=group_
↳keys))
```

List Groups By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.list_groups_by_name()

```
import hvac
client = hvac.Client()

list_response = client.secrets.identity.list_groups_by_name()
group_keys = list_response['data']['keys']
print('The following group names are currently configured: {keys}'.format(keys=group_
↳keys))
```

Create Or Update Group By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.create_or_update_group_by_name()

```
import hvac
client = hvac.Client()

client.secrets.identity.create_or_update_group_by_name(
    name='hvac-group',
    metadata=dict(new_datas='uhuh'),
)
```

Read Group By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.read_group_by_name()

```
import hvac
client = hvac.Client()

read_response = client.secrets.identity.read_group_by_name(
    name='hvac-group',
)
group_id = read_response['data']['id']
print('Group ID for "hvac-group" is: {id}'.format(id=group_id))
```

Delete Group By Name

New in version Vault: 0.11.2

hvac.api.secrets_engines.Identity.delete_group_by_name()

```
import hvac
client = hvac.Client()

client.secrets.identity.delete_group_by_name(
    name='hvac-group',
)
```

Group Alias

Create Or Update Group Alias

hvac.api.secrets_engines.Identity.create_or_update_group_alias()

```
import hvac
client = hvac.Client()

create_response = client.secrets.identity.create_or_update_group_alias(
    name='hvac-group-alias',
    canonical_id=group_id,
    mount_accessor='auth_approle_73c16de3',
)
alias_id = create_response['data']['id']
print('Group alias ID for "hvac-group-alias" is: {id}'.format(id=alias_id))
```

Update Group Alias

hvac.api.secrets_engines.Identity.update_group_alias()

```
import hvac
client = hvac.Client()

client.secrets.identity.update_group_alias(
    alias_id=alias_id,
    name='new-alias-name',
    canonical_id=group_id,
    mount_accessor='auth_approle_73c16de3',
)
```

Read Group Alias

hvac.api.secrets_engines.Identity.read_group_alias()

```
import hvac
client = hvac.Client()

read_response = client.secrets.identity.read_group_alias(
```

(continues on next page)

(continued from previous page)

```
        alias_id=alias_id,
    )
    name = read_response['data']['name']
    print('Name for group alias {id} is: {name}'.format(id=alias_id, name=name))
```

Delete Group Alias

hvac.api.secrets_engines.Identity.delete_group_alias()

```
import hvac
client = hvac.Client()

client.secrets.identity.delete_group_alias(
    alias_id=alias_id,
)
```

List Group Aliases

hvac.api.secrets_engines.Identity.list_group_aliases()

```
import hvac
client = hvac.Client()

list_response = client.secrets.identity.list_group_aliases()
alias_keys = list_response['data']['keys']
print('The following group alias IDs are currently configured: {keys}'.
      ↪format(keys=alias_keys))
```

Lookup

Lookup Entity

hvac.api.secrets_engines.Identity.lookup_entity()

```
import hvac
client = hvac.Client()

lookup_response = client.secrets.identity.lookup_entity(
    name='hvac-entity',
)
entity_id = lookup_response['data']['id']
print('Entity ID for "hvac-entity" is: {id}'.format(id=entity_id))
```

Lookup Group

hvac.api.secrets_engines.Identity.lookup_group()

```
import hvac
client = hvac.Client()

lookup_response = client.secrets.identity.lookup_group(
    name='hvac-group',
)
group_id = lookup_response['data']['id']
print('Group ID for "hvac-entity" is: {id}'.format(id=group_id))
```

2.1.5 PKI

Read CA Certificate

`hvac.api.secrets_engines.pki.read_ca_certificate()`

```
import hvac
client = hvac.Client()

read_ca_certificate_response = client.secrets.pki.read_ca_certificate()
print('Current PKI CA Certificate: {}'.format(read_ca_certificate_response))
```

Read CA Certificate Chain

`hvac.api.secrets_engines.pki.read_ca_certificate_chain()`

```
import hvac
client = hvac.Client()

read_ca_certificate_chain_chain_response = self.client.secrets.pki.read_ca_
↪certificate_chain_chain()
print('Current PKI CA Certificate Chain: {}'.format(read_ca_certificate_chain_
↪response))
```

Read Certificate

`hvac.api.secrets_engines.pki.read_certificate()`

```
import hvac
client = hvac.Client()

read_certificate_response = self.client.secrets.pki.read_certificate(serial='crl')
print('Current PKI CRL: {}'.format(read_certificate_response))
```

List Certificates

`hvac.api.secrets_engines.pki.list_certificates()`

```
import hvac
client = hvac.Client()
```

(continues on next page)

(continued from previous page)

```
list_certificate_response = self.client.secrets.pki.list_certificates()
print('Current certificates (serial numbers): {}'.format(list_certificate_response))
```

Submit CA Information

```
hvac.api.secrets_engines.pki.submit_ca_information()
```

```
import hvac
client = hvac.Client()

submit_ca_information_response = self.client.secrets.pki.submit_ca_information(
    '-----BEGIN RSA PRIVATE KEY-----\n...\n-----END CERTIFICATE-----'
)
```

Read CRL Configuration

```
hvac.api.secrets_engines.pki.read_crl_configuration()
```

```
import hvac
client = hvac.Client()

read_crl_configuration_response = self.client.secrets.pki.read_crl_configuration()
print('CRL configuration: {}'.format(read_crl_configuration_response))
```

Set CRL Configuration

```
hvac.api.secrets_engines.pki.set_crl_configuration()
```

```
import hvac
client = hvac.Client()

set_crl_configuration_response = self.client.secrets.pki.set_crl_configuration(
    expiry='72h',
    disable=False
)
```

Read URLs

```
hvac.api.secrets_engines.pki.read_urls()
```

```
import hvac
client = hvac.Client()

read_urls_response = self.client.secrets.pki.read_urls()
print('Get PKI urls: {}'.format(read_urls_response))
```

Set URLs

```
hvac.api.secrets_engines.pki.set_urls()
```

```
import hvac
client = hvac.Client()

set_urls_response = self.client.secrets.pki.set_urls(
{
    'issuing_certificates': ['http://127.0.0.1:8200/v1/pki/ca'],
    'crl_distribution_points': ['http://127.0.0.1:8200/v1/pki/crl']
}
)
```

Read CRL

`hvac.api.secrets_engines.pki.read_crl()`

```
import hvac
client = hvac.Client()

read_crl_response = self.client.secrets.pki.read_crl()
print('Current CRL: {}'.format(read_crl_response))
```

Rotate CRLs

`hvac.api.secrets_engines.pki.rotate_crl()`

```
import hvac
client = hvac.Client()

rotate_crl_response = self.client.secrets.pki.rotate_crl()
print('Rotate CRL: {}'.format(rotate_crl_response))
```

Generate Intermediate

`hvac.api.secrets_engines.pki.generate_intermediate()`

```
import hvac
client = hvac.Client()

generate_intermediate_response = self.client.secrets.pki.generate_intermediate(
    type='exported',
    common_name='Vault integration tests'
)
print('Intermediate certificate: {}'.format(generate_intermediate_response))
```

Set Signed Intermediate

`hvac.api.secrets_engines.pki.set_signed_intermediate()`

```
import hvac
client = hvac.Client()

set_signed_intermediate_response = self.client.secrets.pki.set_signed_intermediate(
```

(continues on next page)

(continued from previous page)

```
'-----BEGIN CERTIFICATE...'  
)
```

Generate Certificate

`hvac.api.secrets_engines.pki.generate_certificate()`

```
import hvac  
client = hvac.Client()  
  
generate_certificate_response = self.client.secrets.pki.generate_certificate(  
    name='myrole',  
    common_name='test.example.com'  
)  
print('Certificate: {}'.format(generate_certificate_response))
```

Revoke Certificate

`hvac.api.secrets_engines.pki.revoke_certificate()`

```
import hvac  
client = hvac.Client()  
  
revoke_certificate_response = self.client.secrets.pki.revoke_certificate(  
    serial_number='39:dd:2e...'  
)  
print('Certificate: {}'.format(revoke_certificate_response))
```

Create/Update Role

`hvac.api.secrets_engines.pki.create_or_update_role()`

```
import hvac  
client = hvac.Client()  
  
create_or_update_role_response = self.client.secrets.pki.create_or_update_role(  
    'mynewrole',  
    {  
        'ttl': '72h',  
        'allow_localhost': 'false'  
    }  
)  
print('New role: {}'.format(create_or_update_role_response))
```

Read Role

`hvac.api.secrets_engines.pki.read_role()`

```
import hvac
client = hvac.Client()

read_role_response = self.client.secrets.pki.read_role('myrole')
print('Role definition: {}'.format(read_role_response))
```

List Roles

```
hvac.api.secrets_engines.pki.list_roles()
```

```
import hvac
client = hvac.Client()

list_roles_response = self.client.secrets.pki.list_roles()
print('List of available roles: {}'.format(list_roles_response))
```

Delete Role

```
hvac.api.secrets_engines.pki.delete_role()
```

```
import hvac
client = hvac.Client()

delete_role_response = self.client.secrets.pki.delete_role('role2delete')
```

Generate Root

```
hvac.api.secrets_engines.pki.generate_root()
```

```
import hvac
client = hvac.Client()

generate_root_response = self.client.secrets.pki.generate_root(
    type='exported',
    common_name='New root CA'
)
print('New root CA: {}'.format(generate_root_response))
```

Delete Root

```
hvac.api.secrets_engines.pki.delete_root()
```

```
import hvac
client = hvac.Client()

delete_root_response = self.client.secrets.pki.delete_root()
```

Sign Intermediate

```
hvac.api.secrets_engines.pki.sign_intermediate()
```

```
import hvac
client = hvac.Client()

sign_intermediate_response = self.client.secrets.pki.sign_intermediate(
    csr='...',
    common_name='example.com',
)
print('Signed certificate: {}'.format(sign_intermediate_response))
```

Sign Self-Issued

`hvac.api.secrets_engines.pki.sign_self_issued()`

```
import hvac
client = hvac.Client()

sign_self_issued_response = self.client.secrets.pki.sign_self_issued(
    certificate='...'
)
print('Signed certificate: {}'.format(sign_self_issued_response))
```

Sign Certificate

`hvac.api.secrets_engines.pki.sign_certificate()`

```
import hvac
client = hvac.Client()

sign_certificate_response = self.client.secrets.pki.sign_certificate(
    name='myrole',
    csr='...',
    common_name='example.com'
)
print('Signed certificate: {}'.format(sign_certificate_response))
```

Sign Verbatim

`hvac.api.secrets_engines.pki.sign_verbatim()`

```
import hvac
client = hvac.Client()

sign_verbatim_response = self.client.secrets.pki.sign_verbatim(
    name='myrole',
    csr='...'
)
print('Signed certificate: {}'.format(sign_verbatim_response))
```

Tidy

`hvac.api.secrets_engines.pki.tidy()`

```
import hvac
client = hvac.Client()

tidy_response = self.client.secrets.pki.tidy()
```

2.1.6 KV Secrets Engines

The `hvac.api.secrets_engines.Kv` instance under the `Client` class's `kv` attribute is a wrapper to expose either version 1 (`KvV1`) or version 2 of the key/value secrets engines' API methods (`KvV2`). At present, this class defaults to version 2 when accessing methods on the instance.

Setting the Default KV Version

`hvac.api.secrets_engines.KvV1.read_secret()`

```
import hvac
client = hvac.Client()

client.kv.default_kv_version = 1
client.kv.read_secret(path='hvac') # => calls hvac.api.secrets_engines.KvV1.read_
↳secret
```

Explicitly Calling a KV Version Method

`hvac.api.secrets_engines.KvV1.list_secrets()`

```
import hvac
client = hvac.Client()

client.kv.v1.read_secret(path='hvac')
client.kv.v2.read_secret_version(path='hvac')
```

Specific KV Version Usage

KV - Version 1

Note: Every method under the `Kv` class's `v1` attribute includes a `mount_point` parameter that can be used to address the `KvV1` secret engine under a custom mount path. E.g., If enabling the `KvV1` secret engine using Vault's CLI commands via `vault secrets enable -path=my-kvv1 -version=1 kv`, the `mount_point` parameter in `hvac.api.secrets_engines.KvV1()` methods would be set to "my-kvv1".

Read a Secret

`hvac.api.secrets_engines.KvV1.read_secret()`

```

import hvac
client = hvac.Client()

# The following path corresponds, when combined with the mount point, to a full Vault_
↳API route of "v1/secretz/hvac"
mount_point = 'secretz'
secret_path = 'hvac'

read_secret_result = client.secrets.kv.v1.read_secret(
    path=secret_path,
    mount_point=mount_point,
)
print('The "psst" key under the secret path ("/v1/secret/hvac") is: {psst}'.format(
    psst=read_secret_result['data']['psst'],
))

```

List Secrets

hvac.api.secrets_engines.KvV1.list_secrets()

```

import hvac
client = hvac.Client()

list_secrets_result = client.secrets.kv.v1.list_secrets(path='hvac')

print('The following keys found under the selected path ("/v1/secret/hvac"): {keys}'.
↳format(
    keys=', '.join(list_secrets_result['data']['keys']),
))

```

Create or Update a Secret

hvac.api.secrets_engines.KvV1.create_or_update_secret()

```

import hvac
client = hvac.Client()
hvac_secret = {
    'psst': 'this is so secret yall',
}

client.secrets.kv.v1.create_or_update_secret(
    path='hvac',
    secret=hvac_secret,
)

read_secret_result = client.secrets.kv.v1.read_secret(
    path='hvac',
)
print('The "psst" key under the secret path ("/v1/secret/hvac") is: {psst}'.format(
    psst=read_secret_result['data']['psst'],
))

```

Delete a Secret

hvac.api.secrets_engines.KvV1.delete_secret()

```
import hvac
client = hvac.Client()

client.secrets.kv.v1.delete_secret(
    path='hvac',
)

# The following will raise a :py:class:`hvac.exceptions.InvalidPath` exception.
read_secret_result = client.secrets.kv.v1.read_secret(
    path='hvac',
)
```

KV - Version 2

Note: Every method under the *Kv class's v2 attribute* includes a *mount_point* parameter that can be used to address the KvV2 secret engine under a custom mount path. E.g., If enabling the KvV2 secret engine using Vault's CLI commands via *vault secrets enable -path=my-kvv2 -version=2 kv*, the *mount_point* parameter in *hvac.api.secrets_engines.KvV2()* methods would be set to "my-kvv2".

Configuration

hvac.api.secrets_engines.KvV2.configure()

Setting the default *max_versions* for a key/value engine version 2 under a path of *kv*:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.configure(
    max_versions=20,
    mount_point='kv',
)
```

Setting the default *cas_required* (check-and-set required) flag under the implicit default path of *secret*:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.configure(
    cas_required=True,
)
```

Read Configuration

hvac.api.secrets_engines.KvV2.configure()

Reading the configuration of a KV version 2 engine mounted under a path of *kv*:


```

import hvac
client = hvac.Client()

kv_configuration = client.secrets.kv.v2.read_configuration(
    mount_point='kv',
)
print('Config under path "kv": max_versions set to "{max_ver}"'.format(
    max_ver=kv_configuration['data']['max_versions'],
))
print('Config under path "kv": check-and-set require flag set to {cas}'.format(
    cas=kv_configuration['data']['cas_required'],
))

```

Read Secret Versions

hvac.api.secrets_engines.KvV2.read_secret_version()

Read the latest version of a given secret/path (“hvac”):

```

import hvac
client = hvac.Client()

secret_version_response = client.secrets.kv.v2.read_secret_version(
    path='hvac',
)
print('Latest version of secret under path "hvac" contains the following keys: {data}
↪'.format(
    data=secret_version_response['data']['data'].keys(),
))
print('Latest version of secret under path "hvac" created at: {date}'.format(
    date=secret_version_response['data']['metadata']['created_time'],
))
print('Latest version of secret under path "hvac" is version #{ver}'.format(
    ver=secret_version_response['data']['metadata']['version'],
))

```

Read specific version (1) of a given secret/path (“hvac”):

```

import hvac
client = hvac.Client()

secret_version_response = client.secrets.kv.v2.read_secret_version(
    path='hvac',
    version=1,
)
print('Version 1 of secret under path "hvac" contains the following keys: {data}'.
↪format(
    data=secret_version_response['data']['data'].keys(),
))
print('Version 1 of secret under path "hvac" created at: {date}'.format(
    date=secret_version_response['data']['metadata']['created_time'],
))

```

Create/Update Secret

hvac.api.secrets_engines.KvV2.create_or_update_secret()

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.create_or_update_secret(
    path='hvac',
    secret=dict(pssst='this is secret'),
)
```

cas parameter with an argument that doesn't match the current version:

```
import hvac
client = hvac.Client()

# Assuming a current version of "6" for the path "hvac" =>
client.secrets.kv.v2.create_or_update_secret(
    path='hvac',
    secret=dict(pssst='this is secret'),
    cas=5,
) # Raises hvac.exceptions.InvalidRequest
```

cas parameter set to 0 will only succeed if the path hasn't already been written.

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.create_or_update_secret(
    path='hvac',
    secret=dict(pssst='this is secret #1'),
    cas=0,
)

client.secrets.kv.v2.create_or_update_secret(
    path='hvac',
    secret=dict(pssst='this is secret #2'),
    cas=0,
) # => Raises hvac.exceptions.InvalidRequest
```

Patch Existing Secret

Method (similar to the Vault CLI command *vault kv patch*) to update an existing path. Either to add a new key/value to the secret and/or update the value for an existing key. Raises an *hvac.exceptions.InvalidRequest* if the path hasn't been written to previously.

hvac.api.secrets_engines.KvV2.patch()

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.patch(
    path='hvac',
    secret=dict(pssst='this is a patched secret'),
)
```

Delete Latest Version of Secret

hvac.api.secrets_engines.KvV2.delete_latest_version_of_secret()

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.delete_latest_version_of_secret(
    path=hvac,
)
```

Delete Secret Versions

hvac.api.secrets_engines.KvV2.delete_secret_versions()

Marking the first 3 versions of a secret deleted under path “hvac”:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.delete_secret_versions(
    path='hvac',
    versions=[1, 2, 3],
)
```

Undelete Secret Versions

hvac.api.secrets_engines.KvV2.undelete_secret_versions()

Marking the last 3 versions of a secret deleted under path “hvac” as “undeleted”:

```
import hvac
client = hvac.Client()

hvac_path_metadata = client.secrets.kv.v2.read_secret_metadata(
    path='hvac',
)

oldest_version = hvac_path_metadata['data']['oldest_version']
current_version = hvac_path_metadata['data']['current_version']
versions_to_undelete = range(max(oldest_version, current_version - 2), current_
↪version + 1)

client.secrets.kv.v2.undelete_secret_versions(
    path='hvac',
    versions=versions_to_undelete,
)
```

Destroy Secret Versions

hvac.api.secrets_engines.KvV2.destroy_secret_versions()

Destroying the first three versions of a secret under path ‘hvac’:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.destroy_secret_versions(
    path='hvac',
    versions=[1, 2, 3],
)
```

List Secrets

hvac.api.secrets_engines.KvV2.list_secrets()

Listing secrets under the 'hvac' path prefix:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.create_or_update_secret(
    path='hvac/big-ole-secret',
    secret=dict(pssst='this is a large secret'),
)

client.secrets.kv.v2.create_or_update_secret(
    path='hvac/lil-secret',
    secret=dict(pssst='this secret... not so big'),
)

list_response = client.secrets.kv.v2.list_secrets(
    path='hvac',
)

print('The following paths are available under "hvac" prefix: {keys}'.format(
    keys=', '.join(list_response['data']['keys']),
))
```

Read Secret Metadata

hvac.api.secrets_engines.KvV2.read_secret_metadata()

```
import hvac
client = hvac.Client()

hvac_path_metadata = client.secrets.kv.v2.read_secret_metadata(
    path='hvac',
)

print('Secret under path hvac is on version {cur_ver}, with an oldest version of {old_
↪ver}'.format(
    cur_ver=hvac_path_metadata['data']['oldest_version'],
    old_ver=hvac_path_metadata['data']['current_version'],
))
```

Update Metadata

hvac.api.secrets_engines.KvV2.update_metadata()

Set max versions for a given path (“hvac”) to 3:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.update_metadata(
    path='hvac',
    max_versions=3,
)
```

Set cas (check-and-set) parameter as required for a given path (“hvac”):

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.update_metadata(
    path='hvac',
    cas_required=True,
)
```

Delete Metadata and All Versions

hvac.api.secrets_engines.KvV2.delete_metadata_and_all_versions()

Delete all versions and metadata for a given path:

```
import hvac
client = hvac.Client()

client.secrets.kv.v2.delete_metadata_and_all_versions(
    path='hvac',
)
```

2.1.7 Transit

- *Create Key*
- *Read Key*
- *List Keys*
- *Delete Key*
- *Update Key Configuration*
- *Rotate Key*
- *Export Key*
- *Encrypt Data*
- *Decrypt Data*

- *Rewrap Data*
- *Generate Data Key*
- *Generate Random Bytes*
- *Hash Data*
- *Generate Hmac*
- *Sign Data*
- *Verify Signed Data*
- *Backup Key*
- *Restore Key*
- *Trim Key*

Note: The following helper method is used various of the examples included here.

```
import sys

def base64ify(bytes_or_str):
    """Helper method to perform base64 encoding across Python 2.7 and Python 3.X"""
    if sys.version_info[0] >= 3 and isinstance(bytes_or_str, str):
        input_bytes = bytes_or_str.encode('utf8')
    else:
        input_bytes = bytes_or_str

    output_bytes = base64.urlsafe_b64encode(input_bytes)
    if sys.version_info[0] >= 3:
        return output_bytes.decode('ascii')
    else:
        return output_bytes
```

Create Key

`Transit.create_key` (*name*, *convergent_encryption=None*, *derived=None*, *exportable=None*, *allow_plaintext_backup=None*, *key_type=None*, *mount_point='transit'*)

Create a new named encryption key of the specified type.

The values set here cannot be changed after key creation.

Supported methods: POST: `/mount_point/keys/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to create. This is specified as part of the URL.
- **convergent_encryption** (*bool*) – If enabled, the key will support convergent encryption, where the same plaintext creates the same ciphertext. This requires `derived` to be set to true. When enabled, each encryption(/decryption/rewrap/datakey) operation will derive a nonce value rather than randomly generate it.

- **derived** (*bool*) – Specifies if key derivation is to be used. If enabled, all encrypt/decrypt requests to this named key must provide a context which is used for key derivation.
- **exportable** (*bool*) – Enables keys to be exportable. This allows for all the valid keys in the key ring to be exported. Once set, this cannot be disabled.
- **allow_plaintext_backup** (*bool*) – If set, enables taking backup of named key in the plaintext format. Once set, this cannot be disabled.
- **key_type** (*str | unicode*) – Specifies the type of key to create. The currently-supported types are:
 - **aes256-gcm96**: AES-256 wrapped with GCM using a 96-bit nonce size AEAD
 - **chacha20-poly1305**: ChaCha20-Poly1305 AEAD (symmetric, supports derivation and convergent encryption)
 - **ed25519**: ED25519 (asymmetric, supports derivation).
 - **ecdsa-p256**: ECDSA using the P-256 elliptic curve (asymmetric)
 - **rsa-2048**: RSA with bit size of 2048 (asymmetric)
 - **rsa-4096**: RSA with bit size of 4096 (asymmetric)
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.secrets.transit.create_key(name='hvac-key')
```

Read Key

`Transit.read_key` (*name, mount_point='transit'*)

Read information about a named encryption key.

The keys object shows the creation time of each key version; the values are not the keys themselves. Depending on the type of key, different information may be returned, e.g. an asymmetric key will return its public key in a standard format for the type.

Supported methods: GET: `/{mount_point}/keys/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to read. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_key` request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

read_key_response = client.secrets.transit.read_key(name='hvac-key')
latest_version = read_key_response['data']['latest_version']
print('Latest version for key "hvac-key" is: {ver}'.format(ver=latest_version))
```

Example output:

```
Latest version for key "hvac-key" is: 1
```

List Keys

`Transit.list_keys` (*mount_point='transit'*)

List keys.

Only the key names are returned (not the actual keys themselves).

Supported methods: LIST: `/{mount_point}/keys`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `requests.Response`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

list_keys_response = client.secrets.transit.read_key(name='hvac-key')
keys = list_keys_response['data']['keys']
print('Currently configured keys: {keys}'.format(keys=keys))
```

Example output:

```
Currently configured keys: {'1': ...}
```

Delete Key

`Transit.delete_key` (*name, mount_point='transit'*)

Delete a named encryption key.

It will no longer be possible to decrypt any data encrypted with the named key. Because this is a potentially catastrophic operation, the `deletion_allowed` tunable must be set in the key's `/config` endpoint.

Supported methods: DELETE: `/{mount_point}/keys/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to delete. This is specified as part of the URL.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

key_name = 'gonna-delete-this-key'

client.secrets.transit.create_key(
    name=key_name,
)

# Update key subsequently to allow deletion...
client.secrets.transit.update_key_configuration(
    name=key_name,
    deletion_allowed=True,
)

# Finally, delete the key
client.secrets.transit.delete_key(name=key_name)
```

Update Key Configuration

```
Transit.update_key_configuration(name, min_decryption_version=None,
                                min_encryption_version=None, deletion_allowed=None,
                                exportable=None, allow_plaintext_backup=None,
                                mount_point='transit')
```

Tune configuration values for a given key.

These values are returned during a read operation on the named key.

Supported methods: POST: `/{{mount_point}}/keys/{{name}}/config`. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to update configuration for.
- **min_decryption_version** (*int*) – Specifies the minimum version of ciphertext allowed to be decrypted. Adjusting this as part of a key rotation policy can prevent old copies of ciphertext from being decrypted, should they fall into the wrong hands. For signatures, this value controls the minimum version of signature that can be verified against. For HMACs, this controls the minimum version of a key allowed to be used as the key for verification.
- **min_encryption_version** (*int*) – Specifies the minimum version of the key that can be used to encrypt plaintext, sign payloads, or generate HMACs. Must be 0 (which will use the latest version) or a value greater or equal to `min_decryption_version`.
- **deletion_allowed** (*bool*) – Specifies if the key is allowed to be deleted.

- **exportable** (*bool*) – Enables keys to be exportable. This allows for all the valid keys in the key ring to be exported. Once set, this cannot be disabled.
- **allow_plaintext_backup** (*bool*) – If set, enables taking backup of named key in the plaintext format. Once set, this cannot be disabled.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

# allow key "hvac-key" to be exported in subsequent requests
client.secrets.transit.update_key_configuration(
    name='hvac-key',
    exportable=True,
)
```

Rotate Key

Transit.**rotate_key** (*name, mount_point='transit'*)

Rotate the version of the named key.

After rotation, new plaintext requests will be encrypted with the new version of the key. To upgrade ciphertext to be encrypted with the latest version of the key, use the rewrap endpoint. This is only supported with keys that support encryption and decryption operations.

Supported methods: POST: `/{{mount_point}}/keys/{name}/rotate`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to read information about. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')
client.secrets.transit.rotate_key(name='hvac-key')
```

Export Key

Transit.**export_key** (*name, key_type, version=None, mount_point='transit'*)

Return the named key.

The keys object shows the value of the key for each version. If version is specified, the specific version will be returned. If latest is provided as the version, the current key will be provided. Depending on the type of key, different information may be returned. The key must be exportable to support this operation and the version must still be valid.

Supported methods: GET: `/{mount_point}/export/{key_type}/{name}/{version}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to read information about. This is specified as part of the URL.
- **key_type** (*str | unicode*) – Specifies the type of the key to export. This is specified as part of the URL. Valid values are: encryption-key signing-key hmac-key
- **version** (*str | unicode*) – Specifies the version of the key to read. If omitted, all versions of the key will be returned. If the version is set to latest, the current key will be returned.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')
export_key_response = client.secrets.transit.export_key(
    name='hvac-key',
    key_type='hmac-key',
)
print('Exported keys: %s' % export_key_response['data']['keys'])
```

Example output:

```
Exported keys: {...}
```

Encrypt Data

`Transit.decrypt_data` (*name, ciphertext, context=None, nonce=None, batch_input=None, mount_point='transit'*)

Decrypt the provided ciphertext using the named key.

Supported methods: POST: `/{mount_point}/decrypt/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to decrypt against. This is specified as part of the URL.
- **ciphertext** (*str | unicode*) – the ciphertext to decrypt.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.

- **nonce** (*str* | *unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters ‘ciphertext’, ‘context’ and ‘nonce’ are also set, they will be ignored. Format for the input goes like this: [dict(context=“b64_context”, ciphertext=“b64_plaintext”), ...]
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import base64
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

encrypt_data_response = client.secrets.transit.encrypt_data(
    name='hvac-key',
    plaintext=base64ify('hi its me hvac'.encode()),
)
ciphertext = encrypt_data_response['data']['ciphertext']
print('Encrypted plaintext ciphertext is: {cipher}'.format(cipher=ciphertext))
```

Example output:

```
Encrypted plaintext ciphertext is: vault:...
```

Decrypt Data

`Transit.decrypt_data` (*name*, *ciphertext*, *context=None*, *nonce=None*, *batch_input=None*, *mount_point='transit'*)

Decrypt the provided ciphertext using the named key.

Supported methods: POST: /{mount_point}/decrypt/{name}. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to decrypt against. This is specified as part of the URL.
- **ciphertext** (*str* | *unicode*) – the ciphertext to decrypt.
- **context** (*str* | *unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.
- **nonce** (*str* | *unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters ‘ciphertext’, ‘context’ and ‘nonce’ are also set, they will be ignored. Format for the input goes like this: [dict(context=“b64_context”, ciphertext=“b64_plaintext”), ...]

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

decrypt_data_response = client.secrets.transit.decrypt_data(
    name='hvac-key',
    ciphertext=ciphertext,
)
plaintext = decrypt_data_response['data']['plaintext']
print('Decrypted plaintext is: {text}'.format(text=plaintext))
```

Example output:

```
Decrypted plaintext is: ...
```

Rewrap Data

Transit.**rewrap_data** (*name, ciphertext, context=None, key_version=None, nonce=None, batch_input=None, mount_point='transit'*)

Rewrap the provided ciphertext using the latest version of the named key.

Because this never returns plaintext, it is possible to delegate this functionality to untrusted users or scripts.

Supported methods: POST: /{mount_point}/rewrap/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to re-encrypt against. This is specified as part of the URL.
- **ciphertext** (*str | unicode*) – Specifies the ciphertext to re-encrypt.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.
- **key_version** (*int*) – Specifies the version of the key to use for the operation. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **nonce** (*str | unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters ‘ciphertext’, ‘context’ and ‘nonce’ are also set, they will be ignored. Format for the input goes like this: `[dict(context="b64_context", ciphertext="b64_plaintext"), ...]`
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

encrypt_data_response = client.secrets.transit.rewrap_data(
    name='hvac-key',
    ciphertext=ciphertext,
)
rewrapped_ciphertext = encrypt_data_response['data']['ciphertext']
print('Rewrapped ciphertext is: {cipher}'.format(cipher=rewrapped_ciphertext))
```

Example output:

```
Rewrapped ciphertext is: vault:...
```

Generate Data Key

`Transit.generate_data_key` (*name*, *key_type*, *context=None*, *nonce=None*, *bits=None*, *mount_point='transit'*)

Generates a new high-entropy key and the value encrypted with the named key.

Optionally return the plaintext of the key as well. Whether plaintext is returned depends on the path; as a result, you can use Vault ACL policies to control whether a user is allowed to retrieve the plaintext value of a key. This is useful if you want an untrusted user or operation to generate keys that are then made available to trusted users.

Supported methods: POST: `/[mount_point]/datakey/[key_type]/[name]`. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to use to encrypt the datakey. This is specified as part of the URL.
- **key_type** (*str* | *unicode*) – Specifies the type of key to generate. If plaintext, the plaintext key will be returned along with the ciphertext. If wrapped, only the ciphertext value will be returned. This is specified as part of the URL.
- **context** (*str* | *unicode*) – Specifies the key derivation context, provided as a base64-encoded string. This must be provided if derivation is enabled.
- **nonce** (*str* | *unicode*) – Specifies a nonce value, provided as base64 encoded. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+. The value must be exactly 96 bits (12 bytes) long and the user must ensure that for any given context (and thus, any given encryption key) this nonce value is never reused.
- **bits** (*int*) – Specifies the number of bits in the desired key. Can be 128, 256, or 512.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')
gen_key_response = client.secrets.transit.generate_data_key(
    name='hvac-key',
    key_type='plaintext',
)
ciphertext = gen_key_response['data']['ciphertext']
print('Generated data key ciphertext is: {cipher}'.format(cipher=ciphertext))
```

Example output:

```
Generated data key ciphertext is: vault:...
```

Generate Random Bytes

`Transit.generate_random_bytes` (*n_bytes=None, output_format=None, mount_point='transit'*)
Return high-quality random bytes of the specified length.

Supported methods: POST: `/{{mount_point}}/random/{{bytes}}`. Produces: 200 application/json

Parameters

- **n_bytes** (*int*) – Specifies the number of bytes to return. This value can be specified either in the request body, or as a part of the URL.
- **output_format** (*str | unicode*) – Specifies the output encoding. Valid options are hex or base64.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

gen_bytes_response = client.secrets.transit.generate_random_bytes(n_bytes=32)
random_bytes = gen_bytes_response['data']['random_bytes']
print('Here are some random bytes: {bytes}'.format(bytes=random_bytes))
```

Example output:

```
Here are some random bytes: ...
```

Hash Data

`Transit.hash_data` (*hash_input, algorithm=None, output_format=None, mount_point='transit'*)
Return the cryptographic hash of given data using the specified algorithm.

Supported methods: POST: `/{{mount_point}}/hash/{{algorithm}}`. Produces: 200 application/json

Parameters

- **hash_input** (*str* | *unicode*) – Specifies the base64 encoded input data.
- **algorithm** (*str* | *unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **output_format** (*str* | *unicode*) – Specifies the output encoding. This can be either hex or base64.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

hash_data_response = client.secrets.transit.hash_data(
    hash_input=base64ify('hi its me hvac'),
    algorithm='sha2-256',
)
sum = hash_data_response['data']['sum']
print('Hashed data is: {sum}'.format(sum=sum))
```

Example output:

```
Hashed data is: ...
```

Generate Hmac

`Transit.generate_hmac` (*name*, *hash_input*, *key_version=None*, *algorithm=None*, *mount_point='transit'*)

Return the digest of given data using the specified hash algorithm and the named key.

The key can be of any type supported by transit; the raw key will be marshaled into bytes to be used for the HMAC function. If the key is of a type that supports rotation, the latest (current) version will be used.

Supported methods: POST: `/{{mount_point}}/hmac/{{name}}/{{algorithm}}`. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to generate hmac against. This is specified as part of the URL.
- **hash_input** – Specifies the base64 encoded input data.
- **key_version** (*int*) – Specifies the version of the key to use for the operation. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **algorithm** (*str* | *unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

generate_hmac_response = client.secrets.transit.generate_hmac(
    name='hvac-key',
    hash_input=base64ify('hi its me hvac'),
    algorithm='sha2-256',
)
hmac = generate_hmac_response['data']
print("HMAC'd data is: {hmac}".format(hmac=hmac))
```

Example output:

```
HMAC'd data is: {'hmac': 'vault:...'}

```

Sign Data

`Transit.sign_data` (*name*, *hash_input*, *key_version=None*, *hash_algorithm=None*, *context=None*, *prehashed=None*, *signature_algorithm=None*, *marshaling_algorithm=None*, *mount_point='transit'*)

Return the cryptographic signature of the given data using the named key and the specified hash algorithm.

The key must be of a type that supports signing.

Supported methods: POST: `/{{mount_point}}/sign/{{name}}/{{hash_algorithm}}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to use for signing. This is specified as part of the URL.
- **hash_input** (*str | unicode*) – Specifies the base64 encoded input data.
- **key_version** (*int*) – Specifies the version of the key to use for signing. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **hash_algorithm** (*str | unicode*) – Specifies the hash algorithm to use for supporting key types (notably, not including `ed25519` which specifies its own hash algorithm). This can also be specified as part of the URL. Currently-supported algorithms are: `sha2-224`, `sha2-256`, `sha2-384`, `sha2-512`
- **context** (*str | unicode*) – Base64 encoded context for key derivation. Required if key derivation is enabled; currently only available with `ed25519` keys.
- **prehashed** (*bool*) – Set to true when the input is already hashed. If the key type is `rsa-2048` or `rsa-4096`, then the algorithm used to hash the input should be indicated by the

hash_algorithm parameter. Just as the value to sign should be the base64-encoded representation of the exact binary data you want signed, when set, input is expected to be base64-encoded binary hashed data, not hex-formatted. (As an example, on the command line, you could generate a suitable input via `openssl dgst -sha256 -binary | base64`.)

- **signature_algorithm** (*str* | *unicode*) – When using a RSA key, specifies the RSA signature algorithm to use for signing. Supported signature types are: pss, pkcs1v15
- **marshaling_algorithm** (*str* | *unicode*) – Specifies the way in which the signature should be marshaled. This currently only applies to ECDSA keys. Supported types are: asn1, jws
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

key_name = 'hvac-signing-key'

# Note: some key types do no support signing...
# E.g., "key type aes256-gcm96 does not support verification"
client.secrets.transit.create_key(
    name=key_name,
    key_type='ed25519',
)

sign_data_response = client.secrets.transit.sign_data(
    name=key_name,
    hash_input=base64ify('hi its me hvac'),
)
signature = sign_data_response['data']['signature']
print('Signature is: {signature}'.format(signature=signature))
```

Example output:

```
Signature is: vault:...
```

Verify Signed Data

`Transit.verify_signed_data` (*name*, *hash_input*, *signature=None*, *hmac=None*,
hash_algorithm=None, *context=None*, *prehashed=None*,
signature_algorithm=None, *marshaling_algorithm=None*,
mount_point='transit')

Return whether the provided signature is valid for the given data.

Supported methods: POST: `/{mount_point}/verify/{name}/{hash_algorithm}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key that was used to generate the signature or HMAC.
- **hash_input** – Specifies the base64 encoded input data.
- **signature** (*str | unicode*) – Specifies the signature output from the `/transit/sign` function. Either this must be supplied or `hmac` must be supplied.
- **hmac** (*str | unicode*) – Specifies the signature output from the `/transit/hmac` function. Either this must be supplied or `signature` must be supplied.
- **hash_algorithm** (*str | unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **context** (*str | unicode*) – Base64 encoded context for key derivation. Required if key derivation is enabled; currently only available with ed25519 keys.
- **prehashed** (*bool*) – Set to true when the input is already hashed. If the key type is `rsa-2048` or `rsa-4096`, then the algorithm used to hash the input should be indicated by the `hash_algorithm` parameter.
- **signature_algorithm** (*str | unicode*) – When using a RSA key, specifies the RSA signature algorithm to use for signature verification. Supported signature types are: `pss`, `pkcs1v15`
- **marshaling_algorithm** (*str | unicode*) – Specifies the way in which the signature should be marshaled. This currently only applies to ECDSA keys. Supported types are: `asn1`, `jws`
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `requests.Response`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

verify_signed_data_response = client.secrets.transit.verify_signed_data(
    name='hvac-signing-key',
    hash_input=base64ify('hi its me hvac'),
    signature=signature,
)
valid = verify_signed_data_response['data']['valid']
print('Signature is valid?: {valid}'.format(valid=valid))
```

Example output:

```
Signature is valid?: True
```

Backup Key

`Transit.backup_key` (*name, mount_point='transit'*)

Return a plaintext backup of a named key.

The backup contains all the configuration data and keys of all the versions along with the HMAC key. The response from this endpoint can be used with the `/restore` endpoint to restore the key.

Supported methods: GET: `/{mount_point}/backup/{name}`. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Name of the key.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

key_name = 'hvac-key'

# Update the key configuration to allow exporting
client.secrets.transit.update_key_configuration(
    name=key_name,
    exportable=True,
    allow_plaintext_backup=True,
)

backup_key_response = client.secrets.transit.backup_key(
    name=key_name,
)

backed_up_key = backup_key_response['data']['backup']
print('Backed up key: %s' % backed_up_key)
```

Example output:

```
Backed up key: ...
```

Restore Key

`Transit.restore_key` (*backup*, *name=None*, *force=None*, *mount_point='transit'*)

Restore the backup as a named key.

This will restore the key configurations and all the versions of the named key along with HMAC keys. The input to this endpoint should be the output of `/backup` endpoint. For safety, by default the backend will refuse to restore to an existing key. If you want to reuse a key name, it is recommended you delete the key before restoring. It is a good idea to attempt restoring to a different key name first to verify that the operation successfully completes.

Supported methods: POST: `/{mount_point}/restore(/name)`. Produces: 204 (empty body)

Parameters

- **backup** (*str* | *unicode*) – Backed up key data to be restored. This should be the output from the `/backup` endpoint.
- **name** (*str* | *unicode*) – If set, this will be the name of the restored key.

- **force** (*bool*) – If set, force the restore to proceed even if a key by this name already exists.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac

client = hvac.Client(url='https://127.0.0.1:8200')

client.secrets.transit.update_key_configuration(
    name=key_name,
    deletion_allowed=True,
)
delete_resp = client.secrets.transit.delete_key(name=key_name)

# Restore a key after deletion
client.secrets.transit.restore_key(backup=backed_up_key)
```

Trim Key

Transit.**trim_key** (*name, min_version, mount_point='transit'*)

Trims older key versions setting a minimum version for the keyring.

Once trimmed, previous versions of the key cannot be recovered.

Supported methods: POST: `/{{mount_point}}/keys/{{name}}/trim`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to be trimmed.
- **min_version** (*int*) – The minimum version for the key ring. All versions before this version will be permanently deleted. This value can at most be equal to the lesser of `min_decryption_version` and `min_encryption_version`. This is not allowed to be set when either `min_encryption_version` or `min_decryption_version` is set to zero.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

Examples

Note: Transit key trimming was added for Vault versions `>=0.11.4`.

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

key_name = 'hvac-key'

for _ in range(0, 10):
    # Rotate the key a bunch...
    client.secrets.transit.rotate_key(
        name=key_name,
    )

# Set a minimum encryption version
client.secrets.transit.update_key_configuration(
    name=key_name,
    min_decryption_version=3,
    min_encryption_version=5,
)

# Trim any unneeded versions remaining of the key...
client.secrets.transit.trim_key(
    name='hvac-key',
    min_version=3,
)
```

2.2 Auth Methods

2.2.1 Approle

Authentication

```
client.auth_approle('MY_ROLE_ID', 'MY_SECRET_ID')
```

2.2.2 AWS

Contents

- AWS
 - IAM Authentication
 - * *Static Access Key Strings*
 - * *Boto3 Session*
 - * *EC2 Metadata Service*
 - * *Lambda and/or EC2 Instance*
 - * *Caveats For Non-Default AWS Regions*
 - EC2 Authentication
 - * *EC2 Metadata Service*

IAM Authentication

Source reference: `hvac.v1.Client.auth_aws_iam()`

Static Access Key Strings

Various examples of authenticating with static access key strings:

```
import hvac

client = hvac.Client()

client.auth_aws_iam('MY_AWS_ACCESS_KEY_ID', 'MY_AWS_SECRET_ACCESS_KEY')
client.auth_aws_iam('MY_AWS_ACCESS_KEY_ID', 'MY_AWS_SECRET_ACCESS_KEY', 'MY_AWS_
↪SESSION_TOKEN')
client.auth_aws_iam('MY_AWS_ACCESS_KEY_ID', 'MY_AWS_SECRET_ACCESS_KEY', role='MY_ROLE
↪')
```

Boto3 Session

Retrieving credentials from a boto3 Session object:

```
import boto3
import hvac

session = boto3.Session()
credentials = session.get_credentials()

client = hvac.Client()
client.auth_aws_iam(credentials.access_key, credentials.secret_key, credentials.token)
```

EC2 Metadata Service

Retrieving static instance role credentials within an EC2 instance using the EC2 metadata service (the EC2 auth method is probably a better fit for this case, which is outlined below under *EC2 Authentication*):

```
import logging
import requests
from requests.exceptions import RequestException
import hvac

logger = logging.getLogger(__name__)

EC2_METADATA_URL_BASE = 'http://169.254.169.254'

def load_aws_ec2_role_iam_credentials(role_name, metadata_url_base=EC2_METADATA_URL_
↪BASE):
    """
    Requests an ec2 instance's IAM security credentials from the EC2 metadata service.
    :param role_name: Name of the instance's role.
    :param metadata_url_base: IP address for the EC2 metadata service.
    :return: dict, unmarshalled JSON response of the instance's security credentials
    """
```

(continues on next page)

(continued from previous page)

```

    metadata_pkcs7_url = '{base}/latest/meta-data/iam/security-credentials/{role}'.
↪format (
        base=metadata_url_base,
        role=role_name,
    )
    logger.debug("load_aws_ec2_role_iam_credentials connecting to %s" % metadata_
↪pkcs7_url)
    response = requests.get(url=metadata_pkcs7_url)
    response.raise_for_status()
    security_credentials = response.json()
    return security_credentials

credentials = load_aws_ec2_role_iam_credentials('some-instance-role')

client = hvac.Client()
client.auth_aws_iam(credentials['AccessKeyId'], credentials['SecretAccessKey'], ↪
↪credentials['Token'])

```

Lambda and/or EC2 Instance

```

import os
import hvac

def infer_credentials_from_iam_role(iam_role):
    on_lambda = 'AWS_LAMBDA_FUNCTION_NAME' in os.environ
    if on_lambda:
        return os.environ['AWS_ACCESS_KEY_ID'], os.environ['AWS_SECRET_ACCESS_KEY']
    else:
        security_credentials = load_aws_ec2_role_iam_credentials(iam_role)
        return security_credentials['AccessKeyId'], security_credentials[
↪'SecretAccessKey']

access_key_id, secret_access_key = infer_credentials_from_iam_role('some-role')

client = hvac.Client()
client.auth_aws_iam(access_key_id, secret_access_key)

```

Caveats For Non-Default AWS Regions

I.e., calling `hvac.v1.Client.auth_aws_iam()` with a *region* argument other than its default of “**us-east-1**”. For additional background / context on this matter, see the comments at [hvac#251](#) and/or [vault-ruby#161](#).

The following code snippets are for authenticating hosts in the **us-west-1** region:

Note: In order to authenticate to various regions, the AWS auth method configuration needs to be set up with an “endpoint URL” corresponding to the region in question. E.g.: “<https://sts.us-west-1.amazonaws.com>” in the case of this example. Vault defaults to an endpoint of “<https://sts.amazonaws.com>” if not configured with a different endpoint URL.

```

import boto3
import hvac

VAULT_ADDR = os.environ["VAULT_ADDR"]
VAULT_HEADER_VALUE = os.environ["VAULT_HEADER_VALUE"]

client = hvac.Client(url=VAULT_ADDR)

# One-time setup of the credentials / configuration for the Vault server to use.
# Note the explicit region subdomain bit included in the endpoint argument.
client.create_vault_ec2_client_configuration(
    access_key='SOME_ACCESS_KEY_FOR_VAULTS_USE',
    secret_key='SOME_ACCESS_KEY_FOR_VAULTS_USE',
    endpoint='https://sts.us-west-1.amazonaws.com',
)

session = boto3.Session()
creds = session.get_credentials().get_frozen_credentials()
client.auth_aws_iam(
    creds.access_key,
    creds.secret_key,
    creds.token,
    region="us-west-1",
    header_value=VAULT_HEADER_VALUE,
    role='some-role',
    use_token=True,
)

```

EC2 Authentication

Source reference: `hvac.v1.Client.auth_ec2()`

EC2 Metadata Service

Authentication using EC2 instance role credentials and the EC2 metadata service

```

#!/usr/bin/env python
import logging.handlers
import os

import hvac
import requests
from requests.exceptions import RequestException

logger = logging.getLogger(__name__)

VAULT_URL = os.getenv('VAULT_ADDR', 'https://127.0.0.1:8200')
VAULT_CERTS = ('/etc/vault.d/ssl/bundle.crt', '/etc/vault.d/ssl/vault.key')
TOKEN_NONCE_PATH = os.getenv('WP_VAULT_TOKEN_NONCE_PATH', '/root/.vault-token-meta-
↪nonce')
EC2_METADATA_URL_BASE = 'http://169.254.169.254'

```

(continues on next page)

(continued from previous page)

```

def load_aws_ec2_pkcs7_string(metadata_url_base=EC2_METADATA_URL_BASE) :
    """
    Requests an ec2 instance's pkcs7-encoded identity document from the EC2 metadata_
    ↪service.
    :param metadata_url_base: IP address for the EC2 metadata service.
    :return: string, pkcs7-encoded identity document from the EC2 metadata service
    """
    metadata_pkcs7_url = '{base}/latest/dynamic/instance-identity/pkcs7'.
    ↪format(base=metadata_url_base)
    logger.debug("load_aws_ec2_pkcs7_string connecting to %s" % metadata_pkcs7_url)

    response = requests.get(url=metadata_pkcs7_url)
    response.raise_for_status()

    pkcs7 = response.text.replace('\n', '')

    return pkcs7

def load_aws_ec2_nonce_from_disk(token_nonce_path=TOKEN_NONCE_PATH) :
    """
    Helper method to load a previously stored "token_meta_nonce" returned in the
    initial authorization AWS EC2 request from the current instance to our Vault_
    ↪service.
    :param token_nonce_path: string, the full filesystem path to a file containing_
    ↪the instance's
        token meta nonce.
    :return: string, a previously stored "token_meta_nonce"
    """
    logger.debug("Attempting to load vault token meta nonce from path: %s" % token_
    ↪nonce_path)
    try:
        with open(token_nonce_path, 'rb') as nonce_file:
            nonce = nonce_file.readline()
    except IOError:
        logger.warning("Unable to load vault token meta nonce at path: %s" % token_
    ↪nonce_path)
        nonce = None

    logger.debug("Nonce loaded: %s" % nonce)
    return nonce

def write_aws_ec2_nonce_to_disk(token_meta_nonce, token_nonce_path=TOKEN_NONCE_PATH) :
    """
    Helper method to store the current "token_meta_nonce" returned from authorization_
    ↪AWS EC2 request
    from the current instance to our Vault service.
    :return: string, a previously stored "token_meta_nonce"
    :param token_meta_nonce: string, the actual nonce
    :param token_nonce_path: string, the full filesystem path to a file containing_
    ↪the instance's
        token meta nonce.
    :return: None
    """
    logger.debug('Writing nonce "{0}" to file "{1}.".format(token_meta_nonce, token_
    ↪nonce_path))

```

(continues on next page)

(continued from previous page)

```

with open(token_nonce_path, 'w') as nonce_file:
    nonce_file.write(token_meta_nonce)

def auth_ec2(vault_client, pkcs7=None, nonce=None, role=None, mount_point='aws',
↳store_nonce=True):
    """
    Helper method to authenticate to vault using the "auth_ec2" backend.
    :param vault_client: hvac.Client
    :param pkcs7: pkcs7-encoded identity document from the EC2 metadata service
    :param nonce: string, the nonce retruned from the initial AWS EC2 auth request_
↳(if applicable)
    :param role: string, the role/policy to request. Defaults to the current instance
↳'s AMI ID if not provided.
    :param mount_point: string, the path underwhich the AWS EC2 auth backend is_
↳provided
    :param store_nonce: bool, if True, store the nonce received in the auth_ec2_
↳response on disk for later use.
    Especially useful for automated secure introduction.
    :param kwargs: dict, remaining arguments blindly passed through by this lookup_
↳module class
    :return: None
    """
    if pkcs7 is None:
        logger.debug('No pkcs7 argument provided to auth_ec2 backend.')
        logger.debug('Attempting to retrieve information from EC2 metadata service.')
        pkcs7 = load_aws_ec2_pkcs7_string()

    if nonce is None:
        logger.debug('No nonce argument provided to auth_ec2 backend.')
        logger.debug('Attempting to retrieve information from disk.')
        nonce = load_aws_ec2_nonce_from_disk()

    auth_ec2_resp = vault_client.auth_ec2(
        pkcs7=pkcs7,
        nonce=nonce,
        role=role,
        use_token=False,
        mount_point=mount_point
    )

    if store_nonce and 'metadata' in auth_ec2_resp.get('auth', dict()):
        token_meta_nonce = auth_ec2_resp['auth']['metadata'].get('nonce')
        if token_meta_nonce is not None:
            logger.debug('token_meta_nonce received back from auth_ec2 call: %s' %_
↳token_meta_nonce)
            write_aws_ec2_nonce_to_disk(token_meta_nonce)
        else:
            logger.warning('No token meta nonce returned in auth response.')

    return auth_ec2_resp

def get_vault_client(vault_url=VAULT_URL, certs=VAULT_CERTS, verify_certs=True, ec2_
↳role=None):
    """
    Instantiates a hvac / vault client.

```

(continues on next page)

(continued from previous page)

```

    :param vault_url: string, protocol + address + port for the vault service
    :param certs: tuple, Optional tuple of self-signed certs to use for verification
↳with hvac's requests
    :param verify_certs: bool, if True use the provided certs tuple for verification
↳with hvac's requests.
        If False, don't verify SSL with hvac's requests (typically used with local
↳development).
    :param ec2_role: str, Name of the Vault AWS auth backend role to use when
↳retrieving a token (if applicable)
    :return: hvac.Client
    """
    logger.debug('Retrieving a vault (hvac) client...')
    if verify_certs:
        # We use a self-signed certificate for the vault service itself, so we need
↳to include our
        # local ca bundle here for the underlying requests module.
        os.environ['REQUESTS_CA_BUNDLE'] = '/etc/ssl/certs/ca-certificates.crt'
        vault_client = hvac.Client(
            url=vault_url,
            cert=certs,
        )
    else:
        vault_client = hvac.Client(
            url=vault_url,
            verify=False,
        )

    vault_client.token = load_vault_token(vault_client, ec2_role=ec2_role)

    if not vault_client.is_authenticated():
        raise hvac.exceptions.Unauthorized('Unable to authenticate to the Vault
↳service')

    return vault_client

authenticated_vault_client = get_vault_client()

```

2.2.3 Azure

Note: Every method under the Client class's `azure` attribute includes a `mount_point` parameter that can be used to address the Azure auth method under a custom mount path. E.g., If enabling the Azure auth method using Vault's CLI commands via `vault auth enable -path=my-azure azure`, the `mount_point` parameter in `hvac.api.auth_methods.Azure()` methods would be set to "my-azure".

Enabling the Auth Method

```
hvac.v1.Client.enable_auth_backend()
```

```
import hvac
client = hvac.Client()
```

(continues on next page)

(continued from previous page)

```

azure_auth_path = 'company-azure'
description = 'Auth method for use by team members in our company's Azure organization
↪'

if '%s/' % azure_auth_path not in vault_client.list_auth_backends():
    print('Enabling the azure auth backend at mount_point: {path}'.format(
        path=azure_auth_path,
    ))
    client.enable_auth_backend(
        backend_type='azure',
        description=description,
        mount_point=azure_auth_path,
    )

```

Configure

hvac.api.auth_methods.Azure.configure()

```

import os
import hvac
client = hvac.Client()

client.auth.azure.configure(
    tenant_id='my-tenant-id'
    resource='my-resource',
    client_id=os.environ.get('AZURE_CLIENT_ID'),
    client_secret=os.environ.get('AZURE_CLIENT_SECRET'),
)

```

Read Config

hvac.api.auth_methods.Azure.read_config()

```

import hvac
client = hvac.Client()

read_config = client.auth.azure.read_config()
print('The configured tenant_id is: {id}'.format(id=read_config['tenant_id']))

```

Delete Config

hvac.api.auth_methods.Azure.delete_config()

```

import hvac
client = hvac.Client()

client.auth.azure.delete_config()

```

Create a Role

hvac.api.auth_methods.Azure.create_role()

```
import hvac
client = hvac.Client()

client.auth.azure.create_role(
    name='my-role',
    policies=policies,
    bound_service_principal_ids=bound_service_principal_ids,
)
```

Read A Role

hvac.api.auth_methods.Azure.read_role()

```
import hvac
client = hvac.Client()

role_name = 'my-role'
read_role_response = client.auth.azure.read_role(
    name=role_name,
)
print('Policies for role "{name}": {policies}'.format(
    name='my-role',
    policies=', '.join(read_role_response['policies']),
))
```

List Roles

hvac.api.auth_methods.Azure.list_roles()

```
import hvac
client = hvac.Client()

roles = client.auth.azure.list_roles()
print('The following Azure auth roles are configured: {roles}'.format(
    roles=', '.join(roles['keys']),
))
```

Delete A Role

hvac.api.auth_methods.Azure.delete_role()

```
import hvac
client = hvac.Client()

client.auth.azure.delete_role(
    name='my-role',
)
```

Login

hvac.api.auth_methods.Azure.login()

```

import hvac
client = hvac.Client()

client.auth.azure.login(
    role=role_name,
    jwt='Some MST JWT...',
)
client.is_authenticated # ==> returns True

```

2.2.4 GCP

Note: Every method under the Client class's `gcp.auth` attribute includes a `mount_point` parameter that can be used to address the GCP auth method under a custom mount path. E.g., If enabling the GCP auth method using Vault's CLI commands via `vault auth enable -path=my-gcp gcp`, the `mount_point` parameter in `hvac.api.auth.Gcp()` methods would be set to "my-gcp".

Enabling the Auth Method

Source reference: `hvac.v1.Client.enable_auth_backend()`

```

import hvac
client = hvac.Client()

gcp_auth_path = 'company-gcp'
description = 'Auth method for use by team members in our company's Gcp organization'

if '%s/' % gcp_auth_path not in vault_client.list_auth_backends():
    print('Enabling the gcp auth backend at mount_point: {path}'.format(
        path=gcp_auth_path,
    ))
    client.enable_auth_backend(
        backend_type='gcp',
        description=description,
        mount_point=gcp_auth_path,
    )

```

Configure

Source reference: `hvac.api.auth.Gcp.configure()`

```

import hvac
client = hvac.Client()

client.auth.gcp.configure(
    credentials='some signed JSON web token for the Vault server...'
)

```

Read Config

Source reference: `hvac.api.auth.Gcp.read_config()`

```
import hvac
client = hvac.Client()

read_config = client.auth.gcp.read_config()
print('The configured project_id is: {id}'.format(id=read_config['project_id']))
```

Delete Config

Source reference: `hvac.api.auth.Gcp.delete_config()`

```
import hvac
client = hvac.Client()

client.auth.gcp.delete_config()
```

Create Role

Source reference: `hvac.api.auth.Gcp.create_role()`

```
import hvac
client = hvac.Client()

client.auth.gcp.create_role(
    name='some-gcp-role-name',
    role_type='iam',
    project_id='some-gcp-project-id',
    bound_service_accounts=['*'],
)
```

Edit Service Accounts On IAM Role

Source reference: `hvac.api.auth.Gcp.edit_service_accounts_on_iam_role()`

```
import hvac
client = hvac.Client()

client.gcp.edit_service_accounts_on_iam_role(
    name='some-gcp-role-name',
    add=['hvac@appspot.gserviceaccount.com'],
)

client.gcp.edit_service_accounts_on_iam_role(
    name='some-gcp-role-name',
    remove=['disallowed-service-account@appspot.gserviceaccount.com'],
)
```

Edit Labels On GCE Role

Source reference: `hvac.api.auth.Gcp.edit_labels_on_gce_role()`


```
import hvac
client = hvac.Client()

client.gcp.edit_labels_on_gce_role(
    name='some-gcp-role-name',
    add=['some-key:some-value'],
)

client.gcp.edit_labels_on_gce_role(
    name='some-gcp-role-name',
    remove=['some-bad-key:some-bad-value'],
)
```

Read A Role

Source reference: `hvac.api.auth.Gcp.read_role()`

```
import hvac
client = hvac.Client()

read_role_response = client.gcp.read_role(
    name=role_name,
)

print('Policies for role "{name}": {policies}'.format(
    name='my-role',
    policies=', '.join(read_role_response['policies']),
))
```

List Roles

Source reference: `hvac.api.auth.Gcp.list_roles()`

```
import hvac
client = hvac.Client()

roles = client.auth.gcp.list_roles()
print('The following GCP auth roles are configured: {roles}'.format(
    roles=', '.join(roles['keys']),
))
```

Delete A Role

Source reference: `hvac.api.auth.Gcp.delete_role()`

```
import hvac
client = hvac.Client()

client.gcp.delete_role(
)
```

Login

Source reference: `hvac.api.auth.Gcp.login()`

```
import hvac
client = hvac.Client()

client.gcp.login(
    role=role_name,
    jwt='some signed JSON web token...'
)
client.is_authenticated # ==> returns True
```

Example with google-api-python-client Usage

```
import time

import googleapiclient.discovery # pip install google-api-python-client
from google.oauth2 import service_account # pip install google-auth
import hvac # pip install hvac

# First load some previously generated GCP service account key
path_to_sa_json = 'some-service-account-path.json'
credentials = service_account.Credentials.from_service_account_file(path_to_sa_json)
with open(path_to_sa_json, 'r') as f:
    creds = json.load(f)
    project = creds['project_id']
    service_account = creds['client_email']

# Generate a payload for subsequent "signJwt()" call
# Reference: https://google-auth.readthedocs.io/en/latest/reference/google.auth.jwt.html#google.auth.jwt.Credentials
now = int(time.time())
expires = now + 900 # 15 mins in seconds, can't be longer.
payload = {
    'iat': now,
    'exp': expires,
    'sub': service_account,
    'aud': 'vault/my-role'
}
body = {'payload': json.dumps(payload)}
name = f'projects/{project}/serviceAccounts/{service_account}'

# Perform the GCP API call
iam = googleapiclient.discovery.build('iam', 'v1', credentials=credentials)
request = iam.projects().serviceAccounts().signJwt(name=name, body=body)
resp = request.execute()
jwt = resp['signedJwt']

# Perform hvac call to configured GCP auth method
client.auth.gcp.login(
    role='my-role',
    jwt=jwt,
)
```

2.2.5 GitHub

Note: Every method under the `Client` class's `github` attribute includes a `mount_point` parameter that can be used to address the Github auth method under a custom mount path. E.g., If enabling the Github auth method using Vault's CLI commands via `vault auth enable -path=my-github github`, the `mount_point` parameter in `hvac.api.auth_methods.Github()` methods would be set to “my-github”.

Enabling the Auth Method

`hvac.v1.Client.enable_auth_backend()`

```
import hvac
client = hvac.Client()

github_auth_path = 'company-github'
description = 'Auth method for use by team members in our company's Github_
↳organization'

if '%s/' % github_auth_path not in vault_client.list_auth_backends():
    print('Enabling the github auth backend at mount_point: {path}'.format(
        path=github_auth_path,
    ))
    client.enable_auth_backend(
        backend_type='github',
        description=description,
        mount_point=github_auth_path,
    )
```

Configure Connection Parameters

`hvac.api.auth_methods.Github.configure()`

```
import hvac
client = hvac.Client()

client.auth.github.configure(
    organization='our-lovely-company',
    max_ttl='48h', # i.e., A given token can only be renewed for up to 48 hours
)
```

Reading Configuration

`hvac.api.auth_methods.Github.read_configuration()`

```
import hvac
client = hvac.Client()

github_config = client.auth.github.read_configuration()
print('The Github auth method is configured with a ttl of: {ttl}'.format(
    ttl=github_config['data']['ttl']
))
```

Mapping Teams to Policies

hvac.api.auth_methods.Github.map_team()

```
import hvac
client = hvac.Client()

teams = [
    dict(name='some-dev-team', policies=['dev-team']),
    dict(name='admin-team', policies=['administrator']),
]
for team in teams:
    client.auth.github.map_team(
        team_name=team['name'],
        policies=team['policies'],
    )
```

Reading Team Mappings

hvac.api.auth_methods.Github.read_team_mapping()

```
import hvac
client = hvac.Client()

team_name = 'my-super-cool-team'
github_config = client.auth.github.read_team_mapping(
    team_name=team_name,
)
print('The Github team {team} is mapped to the following policies: {policies}'.format(
    team=team_name,
    policies=github_config['data']['value'],
))
```

Mapping Users to Policies

hvac.api.auth_methods.Github.map_user()

```
import hvac
client = hvac.Client()

users = [
    dict(name='some-dev-user', policies=['dev-team']),
    dict(name='some-admin-user', policies=['administrator']),
]
for user in users:
    client.auth.github.map_user(
        user_name=user['name'],
        policies=user['policies'],
    )
```

Reading User Mappings

hvac.api.auth_methods.Github.read_user_mapping()

```
import hvac
client = hvac.Client()

user_name = 'some-dev-user'
github_config = client.auth.github.read_user_mapping(
    user_name=user_name,
)
print('The Github user "{user}" is mapped to the following policies: {policies}'.
      ↪format(
        user=user_name,
        policies=github_config['data']['value'],
      )
)
```

Authentication / Login

```
hvac.api.auth_methods.Github.login()
```

Log in and automatically update the underlying “token” attribute on the *hvac.adapters.Adapter()* instance:

```
import hvac
client = hvac.Client()
login_response = client.auth.github.login(token='some personal github token')
```

2.2.6 Kubernetes

Authentication

```
# Kubernetes (from k8s pod)
f = open('/var/run/secrets/kubernetes.io/serviceaccount/token')
jwt = f.read()
client.auth_kubernetes("example", jwt)
```

2.2.7 LDAP

Note: Every method under the `Client` class's `ldap` attribute includes a `mount_point` parameter that can be used to address the LDAP auth method under a custom mount path. E.g., If enabling the LDAP auth method using Vault's CLI commands via `vault auth enable -path=my-ldap ldap`, the `mount_point` parameter in *hvac.api.auth_methods.Ldap()* methods would be set to “my-ldap”.

Enabling the LDAP Auth Method

```
hvac.v1.Client.enable_auth_backend()
```

```
import hvac
client = hvac.Client()

ldap_auth_path = 'company-ldap'
description = "Auth method for use by team members in our company's LDAP organization"
```

(continues on next page)

(continued from previous page)

```
if '%s/' % ldap_auth_path not in vault_client.sys.list_auth_methods():
    print('Enabling the ldap auth backend at mount_point: {path}'.format(
        path=ldap_auth_path,
    ))
    client.enable_auth_backend(
        backend_type='ldap',
        description=description,
        mount_point=ldap_auth_path,
    )
```

Configure LDAP Auth Method Settings

hvac.api.auth_methods.Ldap.configure()

```
import hvac
client = hvac.Client()

client.auth.ldap.configure(
    user_dn='dc=users,dc=hvac,dc=network',
    group_dn='ou=groups,dc=hvac,dc=network',
    url='ldaps://ldap.hvac.network:12345',
    bind_dn='cn=admin,dc=hvac,dc=network',
    bind_pass='ourverygoodadminpassword'
    user_attr='uid',
    group_attr='cn',
)
```

Reading the LDAP Auth Method Configuration

hvac.api.auth_methods.Ldap.read_configuration()

```
import hvac
client = hvac.Client()

ldap_configuration = client.auth.ldap.read_configuration()
print('The LDAP auth method is configured with a LDAP server URL of: {url}'.format(
    url=ldap_configuration['data']['url']
))
```

Create or Update a LDAP Group Mapping

hvac.api.auth_methods.Ldap.create_or_update_group()

```
import hvac
client = hvac.Client()

client.auth.ldap.create_or_update_group(
    name='some-dudes',
    policies=['policy-for-some-dudes'],
)
```

List LDAP Group Mappings

hvac.api.auth_methods.Ldap.list_groups()

```
import hvac
client = hvac.Client()

ldap_groups = client.auth.ldap.list_groups()
print('The following groups are configured in the LDAP auth method: {groups}'.format(
    groups=', '.join(ldap_groups['data']['keys'])
))
```

Read LDAP Group Mapping

hvac.api.auth_methods.Ldap.read_group()

```
import hvac
client = hvac.Client()

some_dudes_ldap_group = client.auth.ldap.read_group(
    name='somedudes',
)
print('The "somedudes" group in the LDAP auth method are mapped to the following_
↳policies: {policies}'.format(
    policies=', '.join(some_dudes_ldap_group['data']['policies'])
))
```

Deleting a LDAP Group Mapping

hvac.api.auth_methods.Ldap.delete_group()

```
import hvac
client = hvac.Client()

client.auth.ldap.delete_group(
    name='some-group',
)
```

Creating or Updating a LDAP User Mapping

hvac.api.auth_methods.Ldap.create_or_update_user()

```
import hvac
client = hvac.Client()

client.auth.ldap.create_or_update_user(
    username='somedude',
    policies=['policy-for-some-dudes'],
)
```

Listing LDAP User Mappings

hvac.api.auth_methods.Ldap.list_users()

```
import hvac
client = hvac.Client()

ldap_users = client.auth.ldap.list_users()
print('The following users are configured in the LDAP auth method: {users}'.format(
    users=', '.join(ldap_users['data']['keys'])
))
```

Reading a LDAP User Mapping

hvac.api.auth_methods.Ldap.read_user()

```
import hvac
client = hvac.Client()

some_dude_ldap_user = client.auth.ldap.read_user(
    username='somedude'
)
print('The "somedude" user in the LDAP auth method is mapped to the following_
↳policies: {policies}'.format(
    policies=', '.join(some_dude_ldap_user['data']['policies'])
))
```

Deleting a Configured User Mapping

hvac.api.auth_methods.Ldap.delete_user()

```
import hvac
client = hvac.Client()

client.auth.ldap.delete_user(
    username='somedude',
)
```

Authentication / Login

hvac.api.auth_methods.Ldap.login_with_user()

For a LDAP backend mounted under a non-default (ldap) path. E.g., via Vault CLI with *vault auth enable -path=prod-ldap ldap*

```
from getpass import getpass

import hvac

service_account_username = 'someuser'
password_prompt = 'Please enter your password for the LDAP authentication backend: '
service_account_password = getpass(prompt=password_prompt)

client = hvac.Client()

# Here the mount_point parameter corresponds to the path provided when enabling the_
↳backend
```

(continues on next page)

(continued from previous page)

```

client.auth.ldap.login(
    username=service_account_username,
    password=service_account_password,
    mount_point='prod-ldap'
)
print(client.is_authenticated()) # => True

```

2.2.8 MFA

Configure MFA Auth Method Settings

```
hvac.api.auth_methods.Mfa.configure()
```

Note: The legacy/unsupported MFA auth method covered by this class's configuration API route only supports integration with a subset of Vault auth methods. See the list of supported auth methods in this module's "SUPPORTED_AUTH_METHODS" attribute and/or the associated [Vault MFA documentation](#) for additional information.

```

import hvac
client = hvac.Client()

userpass_auth_path = 'some-userpass'

if '%s/' % userpass_auth_path not in vault_client.list_auth_backends():
    print('Enabling the userpass auth backend at mount_point: {path}'.format(
        path=userpass_auth_path,
    ))
    client.enable_auth_backend(
        backend_type='userpass',
        mount_point=userpass_auth_path,
    )

client.auth.mfa.configure(
    mount_point=userpass_auth_path,
)

```

Reading the MFA Auth Method Configuration

```
hvac.api.auth_methods.Mfa.read_configuration()
```

```

import hvac
client = hvac.Client()

mfa_configuration = client.auth.mfa.read_configuration()
print('The MFA auth method is configured with a MFA type of: {mfa_type}'.format(
    mfa_type=mfa_configuration['data']['type']
))

```

Configure Duo MFA Type Access Credentials

hvac.api.auth_methods.Mfa.configure_duo_access()

```
from getpass import getpass

import hvac
client = hvac.Client()

secret_key_prompt = 'Please enter the Duo access secret key to configure: '
duo_access_secret_key = getpass(prompt=secret_key_prompt)

client.auth.mfa.configure_duo_access(
    mount_point=userpass_auth_path,
    host='api-1234abcd.duosecurity.com',
    integration_key='SOME_DUO_IKEY',
    secret_key=duo_access_secret_key,
)
```

Configure Duo MFA Type Behavior

hvac.api.auth_methods.Mfa.configure_duo_behavior()

```
import hvac
client = hvac.Client()

client.auth.mfa.configure_duo_behavior(
    mount_point=userpass_auth_path,
    username_format='%s@hvac.network',
)
```

Read Duo MFA Type Behavior

hvac.api.auth_methods.Mfa.read_duo_behavior_configuration()

```
import hvac
client = hvac.Client()

duo_behavior_config = client.auth.mfa.read_duo_behavior_configuration(
    mount_point=userpass_auth_path,
)
print('The Duo MFA behavior is configured with a username_format of: {username_format}'
      ↪'.format(
    username_format=duo_behavior_config['data']['username_format'],
)
```

Authentication / Login

```
from getpass import getpass

import hvac

login_username = 'someuser'
```

(continues on next page)

(continued from previous page)

```

password_prompt = 'Please enter your password for the userpass (with MFA) '
↳authentication backend: '
login_password = getpass(prompt=password_prompt)
passcode_prompt = 'Please enter your OTP for the userpass (with MFA) authentication '
↳backend: '
userpass_mfa_passcode = getpass(prompt=passcode_prompt)

client = hvac.Client()

# Here the mount_point parameter corresponds to the path provided when enabling the
↳backend
client.auth.mfa.auth_userpass(
    username=login_username,
    password=login_password,
    mount_point=userpass_auth_path,
    passcode=userpass_mfa_passcode,
)
print(client.is_authenticated) # => True

```

2.2.9 Okta

Note: Every method under the `Client` class's `okta` attribute includes a `mount_point` parameter that can be used to address the Okta auth method under a custom mount path. E.g., If enabling the Okta auth method using Vault's CLI commands via `vault secret enable -path=my-okta okta`, the `mount_point` parameter in Source reference: `hvac.api.auth_methods.Okta()` methods would be set to "my-okta".

Enabling the Auth Method

Source reference: `hvac.v1.Client.enable_secret_backend()`

```

import hvac
client = hvac.Client()

okta_path = 'company-okta'
description = 'Auth method for use by team members in our company's Okta organization'

if '%s/' % okta_path not in vault_client.sys.list_auth_methods():
    print('Enabling the okta secret backend at mount_point: {path}'.format(
        path=okta_secret_path,
    ))
    client.enable_secret_backend(
        backend_type='okta',
        description=description,
        mount_point=okta_secret_path,
    )

```

Configure

Source reference: `hvac.api.auth_methods.Okta.configure()`

```
import hvac
client = hvac.Client()

client.auth.okta.configure(
    org_name='hvac-project'
)
```

Read Config

Source reference: `hvac.api.auth_methods.Okta.read_config()`

```
import hvac
client = hvac.Client()

okta_config = client.auth.okta.read_config()
print('The Okta auth method at path /okta has a configured organization name of:
↔{name}'.format(
    name=okta_config['data']['org_name'],
))
```

List Users

Source reference: `hvac.api.auth_methods.Okta.list_users()`

```
import hvac
client = hvac.Client()

users = client.auth.okta.list_users()
print('The following Okta users are registered: {users}'.format(
    users=', '.join(users['data']['keys']),
))
```

Register User

Source reference: `hvac.api.auth_methods.Okta.register_user()`

```
import hvac
client = hvac.Client()

client.auth.okta.register_user(
    username='hvac-person',
    policies=['hvac-admin'],
)
```

Read User

Source reference: `hvac.api.auth_methods.Okta.read_user()`

```
import hvac
client = hvac.Client()
```

(continues on next page)

(continued from previous page)

```
read_user = client.auth.okta.read_user(  
    username='hvac-person',  
)  
print('Okta user "{name}" has the following attached policies: {policies}'.format(  
    name='hvac-person',  
    policies=', '.join(read_user['data']['policies'],  
))
```

Delete User

Source reference: `hvac.api.auth_methods.Okta.delete_user()`

```
import hvac  
client = hvac.Client()  
  
client.auth.okta.delete_user(  
    username='hvac-person'  
)
```

List Groups

Source reference: `hvac.api.auth_methods.Okta.list_groups()`

```
import hvac  
client = hvac.Client()  
  
groups = client.auth.okta.list_groups()  
print('The following Okta groups are registered: {groups}'.format(  
    groups=', '.join(groups['data']['keys']),  
))
```

Register Group

Source reference: `hvac.api.auth_methods.Okta.register_group()`

```
import hvac  
client = hvac.Client()  
  
client.auth.okta.register_group(  
    name='hvac-group',  
    policies=['hvac-group-members'],  
)
```

Read Group

Source reference: `hvac.api.auth_methods.Okta.read_group()`

```
import hvac  
client = hvac.Client()
```

(continues on next page)

(continued from previous page)

```
read_group = client.auth.okta.read_group(
    name='hvac-group',
)
print('Okta group "{name}" has the following attached policies: {policies}'.format(
    name='hvac-group',
    policies=', '.join(read_group['data']['policies']),
))
```

Delete Group

Source reference: `hvac.api.auth_methods.Okta.delete_group()`

```
import hvac
client = hvac.Client()

client.auth.okta.delete_group(
    name='hvac-group',
)
```

Login

Source reference: `hvac.api.auth_methods.Okta.login()`

```
from getpass import getpass

import hvac
client = hvac.Client()

password_prompt = 'Please enter your password for the Okta authentication backend: '
okta_password = getpass(prompt=password_prompt)

client.auth.okta.login(
    username='hvac-person',
    password=okta_password,
)
```

2.2.10 Token

Authentication

```
# Token
client.token = 'MY_TOKEN'
assert client.is_authenticated() # => True
```

Token Management

Token creation and revocation:

```

token = client.create_token(policies=['root'], lease='1h')

current_token = client.lookup_token()
some_other_token = client.lookup_token('xxx')

client.revoke_token('xxx')
client.revoke_token('yyy', orphan=True)

client.revoke_token_prefix('zzz')

client.renew_token('aaa')

```

Lookup and revoke tokens via a token accessor:

```

token = client.create_token(policies=['root'], lease='1h')
token_accessor = token['auth']['accessor']

same_token = client.lookup_token(token_accessor, accessor=True)
client.revoke_token(token_accessor, accessor=True)

```

Wrapping/unwrapping a token:

```

wrap = client.create_token(policies=['root'], lease='1h', wrap_ttl='1m')
result = self.client.unwrap(wrap['wrap_info']['token'])

```

Login with a wrapped token:

```

wrap = client.create_token(policies=['root'], lease='1h', wrap_ttl='1m')
new_client = hvac.Client()
new_client.auth_cubbyhole(wrap['wrap_info']['token'])
assert new_client.token != wrapped_token['wrap_info']['token']

```

2.2.11 Authenticate to different auth backends

```

# App ID
client.auth_app_id('MY_APP_ID', 'MY_USER_ID')

# GitHub
client.auth_github('MY_GITHUB_TOKEN')

# TLS
client = Client(cert=('path/to/cert.pem', 'path/to/key.pem'))
client.auth_tls()

# Non-default mount point (available on all auth types)
client.auth_userpass('MY_USERNAME', 'MY_PASSWORD', mount_point='CUSTOM_MOUNT_POINT')

# Authenticating without changing to new token (available on all auth types)
result = client.auth_github('MY_GITHUB_TOKEN', use_token=False)
print(result['auth']['client_token']) # => u'NEW_TOKEN'

# Custom or unsupported auth type
params = {
    'username': 'MY_USERNAME',
    'password': 'MY_PASSWORD',

```

(continues on next page)

(continued from previous page)

```
'custom_param': 'MY_CUSTOM_PARAM',
}

result = client.login('/v1/auth/CUSTOM_AUTH/login', json=params)

# Logout
client.logout()
```

2.3 System Backend

2.3.1 Audit

- *Examples*
- *List Enabled Audit Devices*
- *Enable Audit Device*
- *Disable Audit Device*
- *Calculate Hash*

Examples

```
audit_devices = client.sys.list_enabled_audit_devices()

options = {
    'path': '/tmp/vault.log',
    'log_raw': True,
}

client.sys.enable_audit_device('file', options=options, path='somefile')
client.sys.disable_audit_device('oldfile')
```

List Enabled Audit Devices

`Audit.list_enabled_audit_devices()`

List enabled audit devices.

It does not list all available audit devices. This endpoint requires sudo capability in addition to any path-specific capabilities.

Supported methods: GET: /sys/audit. Produces: 200 application/json

Returns JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

enabled_audit_devices = client.sys.list_enabled_audit_devices()
print('The following audit devices are enabled: {audit_devices_list}'.format(
    audit_devices_list=', '.join(enabled_audit_devices['data'].keys()),
))
```

Example output:

```
The following audit devices are enabled: somefile/
```

Enable Audit Device

`Audit.enable_audit_device` (*device_type*, *description=None*, *options=None*, *path=None*, *local=None*)

Enable a new audit device at the supplied path.

The path can be a single word name or a more complex, nested path.

Supported methods: PUT: /sys/audit/{path}. Produces: 204 (empty body)

Parameters

- **device_type** (*str* | *unicode*) – Specifies the type of the audit device.
- **description** (*str* | *unicode*) – Human-friendly description of the audit device.
- **options** (*str* | *unicode*) – Configuration options to pass to the audit device itself. This is dependent on the audit device type.
- **path** (*str* | *unicode*) – Specifies the path in which to enable the audit device. This is part of the request URL.
- **local** (*bool*) – Specifies if the audit device is a local only.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

options = {
    'path': '/tmp/vault.audit.log'
}

client.sys.enable_audit_device(
    device_type='file',
    options=options,
    path='tmp-file-audit',
)
```

Disable Audit Device

`Audit.disable_audit_device` (*path*)

Disable the audit device at the given path.

Supported methods: DELETE: /sys/audit/{path}. Produces: 204 (empty body)

Parameters `path` (*str* | *unicode*) – The path of the audit device to delete. This is part of the request URL.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.disable_audit_device(
    path='tmp-file-audit',
)
```

Calculate Hash

`Audit.calculate_hash` (*path*, *input_to_hash*)

Hash the given input data with the specified audit device's hash function and salt.

This endpoint can be used to discover whether a given plaintext string (the input parameter) appears in the audit log in obfuscated form.

Supported methods: POST: /sys/audit-hash/{path}. Produces: 204 (empty body)

Parameters

- **path** (*str* | *unicode*) – The path of the audit device to generate hashes for. This is part of the request URL.
- **input_to_hash** (*str* | *unicode*) – The input string to hash.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

input_to_hash = 'some sort of string thinger'

audit_hash = client.sys.calculate_hash(
    path='tmp-file-audit',
    input_to_hash=input_to_hash,
)
```

(continues on next page)

(continued from previous page)

```
print('The hash for the provided input is: %s' % audit_hash['data']['hash'])
```

Example output:

```
The hash for the provided input is: hmac-sha256:...
```

2.3.2 Auth

- *Examples*
- *List Auth Methods*
- *Enable Auth Method*
- *Disable Auth Method*
- *Read Auth Method Tuning*
- *Tune Auth Method*

Examples

```
methods = client.sys.list_auth_methods()

client.sys.enable_auth_method('userpass', path='customuserpass')
client.sys.disable_auth_method('github')
```

List Auth Methods

`Auth.list_auth_methods()`
List all enabled auth methods.

Supported methods: GET: /sys/auth. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

auth_methods = client.sys.list_auth_methods()
print('The following auth methods are enabled: {auth_methods_list}'.format(
    auth_methods_list=', '.join(auth_methods['data'].keys()),
))
```

Example output:

The following auth methods are enabled: token/

Enable Auth Method

Auth.**enable_auth_method**(*method_type*, *description=None*, *config=None*, *plugin_name=None*, *local=False*, *path=None*, ***kwargs*)

Enable a new auth method.

After enabling, the auth method can be accessed and configured via the auth path specified as part of the URL. This auth path will be nested under the auth prefix.

Supported methods: POST: /sys/auth/{path}. Produces: 204 (empty body)

Parameters

- **method_type** (*str* | *unicode*) – The name of the authentication method type, such as “github” or “token”.
- **description** (*str* | *unicode*) – A human-friendly description of the auth method.
- **config** (*dict*) – Configuration options for this auth method. These are the possible values:
 - **default_lease_ttl**: The default lease duration, specified as a string duration like “5s” or “30m”.
 - **max_lease_ttl**: The maximum lease duration, specified as a string duration like “5s” or “30m”.
 - **audit_non_hmac_request_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the request data object.
 - **audit_non_hmac_response_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the response data object.
 - **listing_visibility**: Specifies whether to show this mount in the UI-specific listing endpoint.
 - **passthrough_request_headers**: Comma-separated list of headers to whitelist and pass from the request to the backend.
- **plugin_name** (*str* | *unicode*) – The name of the auth plugin to use based from the name in the plugin catalog. Applies only to plugin methods.
- **local** (*bool*) – <Vault enterprise only> Specifies if the auth method is a local only. Local auth methods are not replicated nor (if a secondary) removed by replication.
- **path** (*str* | *unicode*) – The path to mount the method on. If not provided, defaults to the value of the “method_type” argument.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.enable_auth_method(
    method_type='github',
    path='github-hvac',
)
```

Disable Auth Method

`Auth.disable_auth_method(path)`

Disable the auth method at the given auth path.

Supported methods: DELETE: `/sys/auth/{path}`. Produces: 204 (empty body)

Parameters `path` (*str* | *unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.

Returns The response of the request.

Return type `requests.Response`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.disable_auth_method(
    path='github-hvac',
)
```

Read Auth Method Tuning

`Auth.read_auth_method_tuning(path)`

Read the given auth path’s configuration.

This endpoint requires sudo capability on the final path, but the same functionality can be achieved without sudo via `sys/mounts/auth/[auth-path]/tune`.

Supported methods: GET: `/sys/auth/{path}/tune`. Produces: 200 application/json

Parameters `path` (*str* | *unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.

Returns The JSON response of the request.

Return type `dict`

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')
response = client.sys.read_auth_method_tuning(
    path='github-hvac',
)

print('The max lease TTL for the auth method under path "github-hvac" is: {max_ttl}'.
      ↪format(
        max_ttl=response['data']['max_lease_ttl'],
      ))
```

Example output:

```
The max lease TTL for the auth method under path "github-hvac" is: 2764800
```

Tune Auth Method

`Auth.tune_auth_method`(*path*, *default_lease_ttl=None*, *max_lease_ttl=None*, *description=None*, *audit_non_hmac_request_keys=None*, *audit_non_hmac_response_keys=None*, *listing_visibility=None*, *passthrough_request_headers=None*, ***kwargs*)

Tune configuration parameters for a given auth path.

This endpoint requires sudo capability on the final path, but the same functionality can be achieved without sudo via `sys/mounts/auth/[auth-path]/tune`.

Supported methods: POST: `/sys/auth/{path}/tune`. Produces: 204 (empty body)

Parameters

- **path** (*str* | *unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.
- **default_lease_ttl** (*int*) – Specifies the default time-to-live. If set on a specific auth path, this overrides the global default.
- **max_lease_ttl** (*int*) – The maximum time-to-live. If set on a specific auth path, this overrides the global default.
- **description** (*str* | *unicode*) – Specifies the description of the mount. This overrides the current stored value, if any.
- **audit_non_hmac_request_keys** (*array*) – Specifies the list of keys that will not be HMAC'd by audit devices in the request data object.
- **audit_non_hmac_response_keys** (*list*) – Specifies the list of keys that will not be HMAC'd by audit devices in the response data object.
- **listing_visibility** (*list*) – Specifies whether to show this mount in the UI-specific listing endpoint. Valid values are “unauth” or “”.
- **passthrough_request_headers** (*list*) – List of headers to whitelist and pass from the request to the backend.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.tune_auth_method(
    path='github-hvac',
    description='The Github auth method for hvac users',
)
```

2.3.3 Health

- [Read Status](#)

Read Status

`Health.read_health_status` (*standby_ok=None, active_code=None, standby_code=None, dr_secondary_code=None, performance_standby_code=None, sealed_code=None, uninit_code=None, method='HEAD'*)

Read the health status of Vault.

This matches the semantics of a Consul HTTP health check and provides a simple way to monitor the health of a Vault instance.

Parameters

- **standby_ok** (*bool*) – Specifies if being a standby should still return the active status code instead of the standby status code. This is useful when Vault is behind a non-configurable load balance that just wants a 200-level response.
- **active_code** (*int*) – The status code that should be returned for an active node.
- **standby_code** (*int*) – Specifies the status code that should be returned for a standby node.
- **dr_secondary_code** (*int*) – Specifies the status code that should be returned for a DR secondary node.
- **performance_standby_code** (*int*) – Specifies the status code that should be returned for a performance standby node.
- **sealed_code** (*int*) – Specifies the status code that should be returned for a sealed node.
- **uninit_code** (*int*) – Specifies the status code that should be returned for a uninitialized node.
- **method** (*str | unicode*) – Supported methods: HEAD: /sys/health. Produces: 000 (empty body) GET: /sys/health. Produces: 000 application/json

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

status = client.sys.read_health_status(method='GET')
print('Vault initialization status is: %s' % status['initialized'])
```

Example output:

```
Vault initialization status is: True
```

2.3.4 Init

- *Read Status*
- *Is Initialized*
- *Initialize*

Read Status

`Init.read_init_status()`

Read the initialization status of Vault.

Supported methods: GET: /sys/init. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac

client = hvac.Client(url='https://127.0.0.1:8200')

read_response = client.sys.read_init_status()
print('Vault initialize status: %s' % read_response['initialized'])
```

Example output:

```
Vault initialize status: True
```

Is Initialized

`Init.is_initialized()`

Determine is Vault is initialized or not.

Returns True if Vault is initialized, False otherwise.

Return type bool

Examples

```
import hvac

client = hvac.Client(url='https://127.0.0.1:8200')

print('Vault initialize status: %s' % client.sys.is_initialized())
```

Example output:

```
Vault initialize status: True
```

Initialize

`Init.initialize` (*secret_shares=5, secret_threshold=3, pgp_keys=None, root_token_pgp_key=None, stored_shares=None, recovery_shares=None, recovery_threshold=None, recovery_pgp_keys=None*)

Initialize a new Vault.

The Vault must not have been previously initialized. The recovery options, as well as the stored shares option, are only available when using Vault HSM.

Supported methods: PUT: /sys/init. Produces: 200 application/json

Parameters

- **secret_shares** (*int*) – The number of shares to split the master key into.
- **secret_threshold** (*int*) – Specifies the number of shares required to reconstruct the master key. This must be less than or equal `secret_shares`. If using Vault HSM with auto-unsealing, this value must be the same as `secret_shares`.
- **pgp_keys** (*list*) – List of PGP public keys used to encrypt the output unseal keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as `secret_shares`.
- **root_token_pgp_key** (*str | unicode*) – Specifies a PGP public key used to encrypt the initial root token. The key must be base64-encoded from its original binary representation.
- **stored_shares** (*int*) – <enterprise only> Specifies the number of shares that should be encrypted by the HSM and stored for auto-unsealing. Currently must be the same as `secret_shares`.
- **recovery_shares** (*int*) – <enterprise only> Specifies the number of shares to split the recovery key into.
- **recovery_threshold** (*int*) – <enterprise only> Specifies the number of shares required to reconstruct the recovery key. This must be less than or equal to `recovery_shares`.
- **recovery_pgp_keys** (*list*) – <enterprise only> Specifies an array of PGP public keys used to encrypt the output recovery keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as `recovery_shares`.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac

client = hvac.Client(url='https://127.0.0.1:8200')

init_result = client.sys.initialize()

root_token = init_result['root_token']
unseal_keys = init_result['keys']
```

When called for a previously initialized Vault cluster, an exception is raised:

```
import hvac

client = hvac.Client(url='https://127.0.0.1:8200')

init_result = client.sys.initialize()
```

Example output:

```
Traceback (most recent call last):
...
hvac.exceptions.InvalidRequest: Vault is already initialized
```

2.3.5 Key

- *Read Root Generation Progress*
- *Start Root Token Generation*
- *Cancel Root Generation*
- *Generate Root*
- *Get Encryption Key Status*
- *Rotate Encryption Key*
- *Read Rekey Progress*
- *Start Rekey*
- *Cancel Rekey*
- *Rekey*
- *Rekey Multi*
- *Read Backup Keys*

Read Root Generation Progress

Key. **read_root_generation_progress** ()

Read the configuration and process of the current root generation attempt.

Supported methods: GET: /sys/generate-root/attempt. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

root_gen_progress = client.sys.read_root_generation_progress()
print('Root generation "started" status: %s' % root_gen_progress['started'])
```

Example output:

```
Root generation "started" status: ...
```

Start Root Token Generation

Key. **start_root_token_generation** (*otp=None, pgp_key=None*)

Initialize a new root generation attempt.

Only a single root generation attempt can take place at a time. One (and only one) of *otp* or *pgp_key* are required.

Supported methods: PUT: /sys/generate-root/attempt. Produces: 200 application/json

Parameters

- **otp** (*str* | *unicode*) – Specifies a base64-encoded 16-byte value. The raw bytes of the token will be XOR'd with this value before being returned to the final unseal key provider.
- **pgp_key** (*str* | *unicode*) – Specifies a base64-encoded PGP public key. The raw bytes of the token will be encrypted with this value before being returned to the final unseal key provider.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
from tests.utils import get_generate_root_otp

client = hvac.Client(url='https://127.0.0.1:8200')

new_otp = get_generate_root_otp()
start_generate_root_response = client.sys.start_root_token_generation(
    otp=new_otp,
```

(continues on next page)

(continued from previous page)

```
)  
nonce = start_generate_root_response['nonce']  
print('Nonce for root generation is: %s' % nonce)
```

Example output:

```
Nonce for root generation is: ...
```

Cancel Root Generation

Key **.cancel_root_generation()**

Cancel any in-progress root generation attempt.

This clears any progress made. This must be called to change the OTP or PGP key being used.

Supported methods: DELETE: /sys/generate-root/attempt. Produces: 204 (empty body)

Returns The response of the request.

Return type request.Response

Examples

```
import hvac  
client = hvac.Client(url='https://127.0.0.1:8200')  
  
client.sys.cancel_root_generation()
```

Generate Root

Key **.generate_root(key, nonce)**

Enter a single master key share to progress the root generation attempt.

If the threshold number of master key shares is reached, Vault will complete the root generation and issue the new token. Otherwise, this API must be called multiple times until that threshold is met. The attempt nonce must be provided with each call.

Supported methods: PUT: /sys/generate-root/update. Produces: 200 application/json

Parameters

- **key** (*str* | *unicode*) – Specifies a single master key share.
- **nonce** (*str* | *unicode*) – The nonce of the attempt.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.generate_root(
    key=key,
    nonce=nonce,
)
```

Get Encryption Key Status

Client.**key_status**

GET /sys/key-status

Returns Information about the current encryption key used by Vault.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

print('Encryption key term is: %s' % client.key_status['term'])
```

Example output:

```
Encryption key term is: 1
```

Rotate Encryption Key

Key.**rotate_encryption_key**()

Trigger a rotation of the backend encryption key.

This is the key that is used to encrypt data written to the storage backend, and is not provided to operators. This operation is done online. Future values are encrypted with the new key, while old values are decrypted with previous encryption keys.

This path requires sudo capability in addition to update.

Supported methods: PUT: /sys/rotate. Produces: 204 (empty body)

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.rotate_encryption_key()
```

Read Rekey Progress

Key.**read_rekey_progress** (*recovery_key=False*)

Read the configuration and progress of the current rekey attempt.

Supported methods: GET: /sys/rekey-recovery-key/init. Produces: 200 application/json GET: /sys/rekey/init. Produces: 200 application/json

Parameters **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

print('Rekey "started" status is: %s' % client.sys.read_rekey_progress()['started'])
```

Example output:

```
Rekey "started" status is: False
```

Start Rekey

Key.**start_rekey** (*secret_shares=5, secret_threshold=3, pgp_keys=None, backup=False, require_verification=False, recovery_key=False*)

Initializes a new rekey attempt.

Only a single recovery key rekeyattempt can take place at a time, and changing the parameters of a rekey requires canceling and starting a new rekey, which will also provide a new nonce.

Supported methods: PUT: /sys/rekey/init. Produces: 204 (empty body) PUT: /sys/rekey-recovery-key/init. Produces: 204 (empty body)

Parameters

- **secret_shares** (*int*) – Specifies the number of shares to split the master key into.
- **secret_threshold** (*int*) – Specifies the number of shares required to reconstruct the master key. This must be less than or equal to secret_shares.
- **pgp_keys** (*list*) – Specifies an array of PGP public keys used to encrypt the output unseal keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as secret_shares.
- **backup** (*bool*) – Specifies if using PGP-encrypted keys, whether Vault should also store a plaintext backup of the PGP-encrypted keys at core/unseal-keys-backup in the physical storage backend. These can then be retrieved and removed via the sys/rekey/backup endpoint.
- **require_verification** (*bool*) – This turns on verification functionality. When verification is turned on, after successful authorization with the current unseal keys, the new unseal keys are returned but the master key is not actually rotated. The new keys must be

provided to authorize the actual rotation of the master key. This ensures that the new keys have been successfully saved and protects against a risk of the keys being lost after rotation but before they can be persisted. This can be used with or without `pgp_keys`, and when used with it, it allows ensuring that the returned keys can be successfully decrypted before committing to the new shares, which the backup functionality does not provide.

- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON dict of the response.

Return type dict | request.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

rekey_response = client.sys.start_rekey()
nonce = rekey_response['nonce']
print('Nonce for rekey is: %s' % nonce)
```

Example output:

```
Nonce for rekey is: ...
```

Cancel Rekey

`Key.cancel_rekey` (*recovery_key=False*)

Cancel any in-progress rekey.

This clears the rekey settings as well as any progress made. This must be called to change the parameters of the rekey.

Note: Verification is still a part of a rekey. If rekeying is canceled during the verification flow, the current unseal keys remain valid.

Supported methods: DELETE: `/sys/rekey/init`. Produces: 204 (empty body) DELETE: `/sys/rekey-recovery-key/init`. Produces: 204 (empty body)

Parameters **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.cancel_rekey()
```

Rekey

Key.**rekey** (*key*, *nonce=None*, *recovery_key=False*)

Enter a single recovery key share to progress the rekey of the Vault.

If the threshold number of recovery key shares is reached, Vault will complete the rekey. Otherwise, this API must be called multiple times until that threshold is met. The rekey nonce operation must be provided with each call.

Supported methods: PUT: /sys/rekey/update. Produces: 200 application/json PUT: /sys/rekey-recovery-key/update. Produces: 200 application/json

Parameters

- **key** (*str* | *unicode*) – Specifies a single recovery share key.
- **nonce** (*str* | *unicode*) – Specifies the nonce of the rekey operation.
- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.rekey(
    key=key,
    nonce=nonce,
)
```

Rekey Multi

Key.**rekey_multi** (*keys*, *nonce=None*, *recovery_key=False*)

Enter multiple recovery key shares to progress the rekey of the Vault.

If the threshold number of recovery key shares is reached, Vault will complete the rekey.

Parameters

- **keys** (*list*) – Specifies multiple recovery share keys.
- **nonce** (*str* | *unicode*) – Specifies the nonce of the rekey operation.
- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The last response of the rekey request.

Return type response.Request

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.rekey_multi(
    keys,
    nonce=nonce,
)
```

Read Backup Keys

`Key.read_backup_keys` (*recovery_key=False*)

Retrieve the backup copy of PGP-encrypted unseal keys.

The returned value is the nonce of the rekey operation and a map of PGP key fingerprint to hex-encoded PGP-encrypted key.

Supported methods: PUT: `/sys/rekey/backup`. Produces: 200 application/json PUT: `/sys/rekey-recovery-key/backup`. Produces: 200 application/json

Parameters `recovery_key` (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')
rekey_response = client.sys.start_rekey(
    secret_shares=1,
    secret_threshold=1,
    pgp_keys=pgp_keys,
    backup=True,
)
nonce = rekey_response['nonce']

client.sys.rekey_multi(
    keys,
    nonce=nonce,
)

print('Backup keys are: %s' % client.sys.read_backup_keys()['data']['keys'])
```

Example output:

```
Backup keys are: {'...': [...]}
```

2.3.6 Leader

- *Read Leader Status*

Read Leader Status

`Leader.read_leader_status()`

Read the high availability status and current leader instance of Vault.

Supported methods: GET: /sys/leader. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

status = client.sys.read_leader_status()
print('HA status is: %s' % status['ha_enabled'])
```

Example output:

```
HA status is: False
```

2.3.7 Lease

- *View and Manage Leases*
- *Read Lease*
- *List Leases*
- *Renew Lease*
- *Revoke Lease*
- *Revoke Prefix*
- *Revoke Force*

View and Manage Leases

Read a lease:

```
>>> read_lease_response = client.sys.read_lease(lease_id=lease_id)
>>> print('Expire time for lease ID {id} is: {expire_time}'.format(
...     id=lease_id,
...     expire_time=read_lease_response['data']['expire_time'],
... ))
Expire time for lease ID pki/issue/my-role/... is: 20...
```

Renewing a lease:

```
>>> renew_lease_resp = client.sys.renew_lease(lease_id=lease_id)
>>> print('Lease ID: "{id}" renewed, lease duration: "{duration}"'.format(
...     id=renew_lease_resp['lease_id'],
...     duration=renew_lease_resp['lease_duration'],
... ))
Lease ID: "pki/issue/my-role/d05138a2-edeb-889d-db98-2057ecd5138f" renewed, lease_
↳duration: "2764790"
```

Revoking a lease:

```
>>> client.sys.revoke_lease(lease_id=lease_id)
<Response [204]>
```

Read Lease

Lease.**read_lease** (*lease_id*)

Retrieve lease metadata.

Supported methods: PUT: /sys/leases/lookup. Produces: 200 application/json

Parameters **lease_id** (*str* | *unicode*) – the ID of the lease to lookup.

Returns Parsed JSON response from the leases PUT request

Return type dict.

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

read_lease_resp = client.sys.read_lease(
    lease_id=lease_id,
)

# expire_time in the form of something like: 2019-02-25T07:41:30.000038-06:00
print('Current expire time for lease ID {id} is: {expires}'.format(
    id=lease_id,
    expires=read_lease_resp['data']['expire_time'],
))
```

Example output:

```
Current expire time for lease ID pki/issue/my-role/... is: ...
```

List Leases

Lease.**list_leases** (*prefix*)

Retrieve a list of lease ids.

Supported methods: LIST: /sys/leases/lookup/{prefix}. Produces: 200 application/json

Parameters **prefix** (*str* | *unicode*) – Lease prefix to filter list by.

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

list_leases_response = client.sys.list_leases(
    prefix='pki',
)
print('The follow lease keys are active under the "pki" prefix: %s' % list_leases_
      ↪response['data']['keys'])
```

Example output:

```
The follow lease keys are active under the "pki" prefix: ['issue/']
```

Renew Lease

Lease.**renew_lease** (*lease_id*, *increment=None*)

Renew a lease, requesting to extend the lease.

Supported methods: PUT: /sys/leases/renew. Produces: 200 application/json

Parameters

- **lease_id** (*str* | *unicode*) – The ID of the lease to extend.
- **increment** (*int*) – The requested amount of time (in seconds) to extend the lease.

Returns The JSON response of the request

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.renew_lease(
    lease_id=lease_id,
    increment=500,
)
```

Revoke Lease

Lease.**revoke_lease** (*lease_id*)

Revoke a lease immediately.

Supported methods: PUT: /sys/leases/revoke. Produces: 204 (empty body)

Parameters **lease_id** (*str* | *unicode*) – Specifies the ID of the lease to revoke.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.revoke_lease(
    lease_id=lease_id,
)
```

Revoke Prefix

Lease.**revoke_prefix** (*prefix*)

Revoke all secrets (via a lease ID prefix) or tokens (via the tokens' path property) generated under a given prefix immediately.

This requires sudo capability and access to it should be tightly controlled as it can be used to revoke very large numbers of secrets/tokens at once.

Supported methods: PUT: /sys/leases/revoke-prefix/{prefix}. Produces: 204 (empty body)

Parameters **prefix** (*str* | *unicode*) – The prefix to revoke.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.revoke_prefix(
    prefix='pki',
)
```

Revoke Force

Lease.**revoke_force** (*prefix*)

Revoke all secrets or tokens generated under a given prefix immediately.

Unlike `revoke_prefix`, this path ignores backend errors encountered during revocation. This is potentially very dangerous and should only be used in specific emergency situations where errors in the backend or the connected backend service prevent normal revocation.

Supported methods: PUT: /sys/leases/revoke-force/{prefix}. Produces: 204 (empty body)

Parameters **prefix** (*str* | *unicode*) – The prefix to revoke.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.revoke_force(
    prefix='pki',
)
```

2.3.8 Mount

- *Manipulate secret backends*
- *List Mounted Secrets Engines*
- *Enable Secrets Engine*
- *Disable Secrets Engine*
- *Read Mount Configuration*
- *Tune Mount Configuration*
- *Move Backend*

Manipulate secret backends

```
backends = client.sys.list_mounted_secrets_engines()['data']

client.sys.enable_secrets_engine('aws', path='aws-us-east-1')
client.sys.disable_secrets_engine('mysql')

client.sys.tune_mount_configuration(path='test', default_lease_ttl='3600s', max_lease_
↳ttl='8600s')
client.sys.read_mount_configuration(path='test')

client.sys.move_backend('aws-us-east-1', 'aws-east')
```

List Mounted Secrets Engines

`Mount.list_mounted_secrets_engines()`

Lists all the mounted secrets engines.

Supported methods: POST: /sys/mounts. Produces: 200 application/json

Returns JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

secrets_engines_list = client.sys.list_mounted_secrets_engines(['data'])
print('The following secrets engines are mounted: %s' % ', '.join(sorted(secrets_
↪ engines_list.keys()))
```

Example output:

```
The following secrets engines are mounted: cubbyhole/, identity/, secret/, sys/
```

Enable Secrets Engine

`Mount.enable_secrets_engine` (*backend_type*, *path=None*, *description=None*, *config=None*, *plugin_name=None*, *options=None*, *local=False*, *seal_wrap=False*, ***kwargs*)

Enable a new secrets engine at the given path.

Supported methods: POST: /sys/mounts/{path}. Produces: 204 (empty body)

Parameters

- **backend_type** (*str* | *unicode*) – The name of the backend type, such as “github” or “token”.
- **path** (*str* | *unicode*) – The path to mount the method on. If not provided, defaults to the value of the “method_type” argument.
- **description** (*str* | *unicode*) – A human-friendly description of the mount.
- **config** (*dict*) – Configuration options for this mount. These are the possible values:
 - **default_lease_ttl**: The default lease duration, specified as a string duration like “5s” or “30m”.
 - **max_lease_ttl**: The maximum lease duration, specified as a string duration like “5s” or “30m”.
 - **force_no_cache**: Disable caching.
 - **plugin_name**: The name of the plugin in the plugin catalog to use.
 - **audit_non_hmac_request_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the request data object.
 - **audit_non_hmac_response_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the response data object.
 - **listing_visibility**: Specifies whether to show this mount in the UI-specific listing endpoint. (“unauth” or “hidden”)
 - **passthrough_request_headers**: Comma-separated list of headers to whitelist and pass from the request to the backend.
- **options** (*dict*) – Specifies mount type specific options that are passed to the backend.
 - **version**: <KV> The version of the KV to mount. Set to “2” for mount KV v2.

- **plugin_name** (*str | unicode*) – Specifies the name of the plugin to use based from the name in the plugin catalog. Applies only to plugin backends.
- **local** (*bool*) – <Vault enterprise only> Specifies if the auth method is a local only. Local auth methods are not replicated nor (if a secondary) removed by replication.
- **seal_wrap** (*bool*) – <Vault enterprise only> Enable seal wrapping for the mount.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.enable_secrets_engine(
    backend_type='kv',
    path='hvac-kv',
)
```

Disable Secrets Engine

Mount.**disable_secrets_engine** (*path*)

Disable the mount point specified by the provided path.

Supported methods: DELETE: /sys/mounts/{path}. Produces: 204 (empty body)

Parameters path (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.disable_secrets_engine(
    path='hvac-kv',
)
```

Read Mount Configuration

Mount.**read_mount_configuration** (*path*)

Read the given mount's configuration.

Unlike the mounts endpoint, this will return the current time in seconds for each TTL, which may be the system default or a mount-specific value.

Supported methods: GET: /sys/mounts/{path}/tune. Produces: 200 application/json

Parameters `path` (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.

Returns The JSON response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

secret_backend_tuning = client.sys.read_mount_configuration(path='hvac-kv')
print('The max lease TTL for the "hvac-kv" backend is: {}'.format(
    max_lease_ttl=secret_backend_tuning['data']['max_lease_ttl'],
))
```

Example output:

```
The max lease TTL for the "hvac-kv" backend is: 2764800
```

Tune Mount Configuration

`Mount.tune_mount_configuration` (*path*, *default_lease_ttl=None*, *max_lease_ttl=None*, *description=None*, *audit_non_hmac_request_keys=None*, *audit_non_hmac_response_keys=None*, *listing_visibility=None*, *passthrough_request_headers=None*, *options=None*, *force_no_cache=None*, ***kwargs*)

Tune configuration parameters for a given mount point.

Supported methods: POST: /sys/mounts/{path}/tune. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.
- **mount_point** (*str*) – The path the associated secret backend is mounted
- **description** (*str*) – Specifies the description of the mount. This overrides the current stored value, if any.
- **default_lease_ttl** (*int*) – Default time-to-live. This overrides the global default. A value of 0 is equivalent to the system default TTL
- **max_lease_ttl** (*int*) – Maximum time-to-live. This overrides the global default. A value of 0 are equivalent and set to the system max TTL.
- **audit_non_hmac_request_keys** (*list*) – Specifies the comma-separated list of keys that will not be HMAC'd by audit devices in the request data object.
- **audit_non_hmac_response_keys** (*list*) – Specifies the comma-separated list of keys that will not be HMAC'd by audit devices in the response data object.
- **listing_visibility** (*str*) – Specifies whether to show this mount in the UI-specific listing endpoint. Valid values are “unauth” or “”.

- **passthrough_request_headers** (*str*) – Comma-separated list of headers to whitelist and pass from the request to the backend.
- **options** (*dict*) – Specifies mount type specific options that are passed to the backend.
 - **version**: <KV> The version of the KV to mount. Set to “2” for mount KV v2.
- **force_no_cache** (*bool*) – Disable caching.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response from the request.

Return type request.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.tune_mount_configuration(
    path='hvac-kv',
    default_lease_ttl='3600s',
    max_lease_ttl='8600s',
)
```

Move Backend

Mount **.move_backend** (*from_path, to_path*)

Move an already-mounted backend to a new mount point.

Supported methods: POST: /sys/remount. Produces: 204 (empty body)

Parameters

- **from_path** (*str | unicode*) – Specifies the previous mount point.
- **to_path** (*str | unicode*) – Specifies the new destination mount point.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.move_backend(
    from_path='hvac-kv',
    to_path='kv-hvac',
)
```

2.3.9 Namespace

- *Create Namespace*
- *List Namespaces*
- *Delete Namespace*

Create Namespace

Namespace.**create_namespace** (*path*)

Create a namespace at the given path.

Supported methods: POST: /sys/namespaces/{path}. Produces: 200 application/json

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

# Create namespace team1 where team1 is a child of root
client.sys.create_namespace(path="team1")

# Create namespace team1/app1 where app1 is a child of team1
client2 = hvac.Client(url='https://127.0.0.1:8200', namespace="team1")
client2.sys.create_namespace(path="app1")
```

Example output:

```
print(client.sys.create_namespace(path="team1")) {"request_id": "<redacted>","lease_id":"","renewable":false,"lease_duration":0}
print(client2.sys.create_namespace(path="app1")) {"request_id": "<redacted>","lease_id":"","renewable":false,"lease_duration":0}
```

List Namespaces

Namespace.**list_namespaces** ()

Lists all the namespaces.

Supported methods: LIST: /sys/namespaces. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')
client.sys.create_namespace(path='testns')

client.sys.list_namespaces()
```

Example output:

```
print(client.sys.list_namespaces()) {"request_id": "<redacted>", "lease_id": "", "renewable": false, "lease_duration": 0, "data": {"key_i
```

Delete Namespace

Namespace.**delete_namespace** (*path*)

Delete a namespaces. You cannot delete a namespace with existing child namespaces.

Supported methods: DELETE: /sys/namespaces. Produces: 204 (empty body)

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac

# Delete namespace app1 where app1 is a child of team1
client2 = hvac.Client(url='https://127.0.0.1:8200', namespace="team1")
client2.sys.delete_namespace(path="app1")

# Delete namespace team1
client = hvac.Client(url='https://127.0.0.1:8200')
client.sys.delete_namespace(path="team1")
```

2.3.10 Policy

- *Manipulate policies*
- *List Policies*
- *Read Policy*
- *Create Or Update Policy*
- *Delete Policy*

Manipulate policies

```
policies = client.sys.list_policies()['data']['policies'] # => ['root']

policy = ""
path "sys" {
```

(continues on next page)

(continued from previous page)

```

    capabilities = ["deny"]
}

path "secret/*" {
    capabilities = ["read", "list"]
}

path "secret/foo" {
    capabilities = ["create", "read", "update", "delete", "list"]
}
"""

client.sys.create_or_update_policy(
    name='secret-writer',
    policy=policy,
)

client.sys.delete_policy('oldthing')

# The get_policy method offers some additional features and is available in the
# Client class.
policy = client.get_policy('mypolicy')

# Requires pyhcl to automatically parse HCL into a Python dictionary
policy = client.get_policy('mypolicy', parse=True)

```

Using Python Variable(s) In Policy Rules

```

import hvac

client = hvac.Client(url='https://127.0.0.1:8200')

key = 'some-key-string'

policy_body = """
path "transit/encrypt/%s" {
    capabilities = ["update"]
}
""" % key

client.sys.create_or_update_policy(
    name='my-policy-name',
    policy=policy_body,
)

```

List Policies

`Policy.list_policies()`

List all configured policies.

Supported methods: GET: /sys/policy. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

list_policies_resp = client.sys.list_policies()['data']['policies']
print('List of currently configured policies: %s' % ', '.join(list_policies_resp))
```

Example output:

```
List of currently configured policies: default, my-policy-name, secret-writer, root
```

Read Policy

`Policy.read_policy` (*name*)

Retrieve the policy body for the named policy.

Supported methods: GET: `/sys/policy/{name}`. Produces: 200 application/json

Parameters `name` (*str* | *unicode*) – The name of the policy to retrieve.

Returns The response of the request

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

hvac_policy_rules = client.sys.read_policy(name='secret-writer')['data']['rules']
print('secret-writer policy rules:\n%s' % hvac_policy_rules)
```

Example output:

```
secret-writer policy rules:

path "sys" {
  capabilities = ["deny"]
}

path "secret/*" {
  capabilities = ["read", "list"]
}

path "secret/foo" {
  capabilities = ["create", "read", "update", "delete", "list"]
}
...
```

Create Or Update Policy

`Policy.create_or_update_policy` (*name*, *policy*, *pretty_print=True*)

Add a new or update an existing policy.

Once a policy is updated, it takes effect immediately to all associated users.

Supported methods: PUT: /sys/policy/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the policy to create.
- **policy** (*str* | *unicode* | *dict*) – Specifies the policy document.
- **pretty_print** (*bool*) – If True, and provided a dict for the policy argument, send the policy JSON to Vault with “pretty” formatting.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

policy = '''
  path "sys" {
    capabilities = ["deny"]
  }
  path "secret" {
    capabilities = ["create", "read", "update", "delete", "list"]
  }
'''
client.sys.create_or_update_policy(
    name='secret-writer',
    policy=policy,
)
```

Delete Policy

`Policy.delete_policy` (*name*)

Delete the policy with the given name.

This will immediately affect all users associated with this policy.

Supported methods: DELETE: /sys/policy/{name}. Produces: 204 (empty body)

Parameters **name** (*str* | *unicode*) – Specifies the name of the policy to delete.

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.delete_policy(
```

(continues on next page)

(continued from previous page)

```
name='secret-writer',  
)
```

2.3.11 Seal

- *Seal Status*
- *Is Sealed*
- *Read Seal Status*
- *Seal*
- *Submit Unseal Key*
- *Submit Unseal Keys*

Seal Status

`Client.seal_status`

Read the seal status of the Vault.

This is an unauthenticated endpoint.

Supported methods: GET: /sys/seal-status. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac  
client = hvac.Client(url='https://127.0.0.1:8200')  
  
print('Is Vault sealed: %s' % client.seal_status['sealed'])
```

Example output:

```
Is Vault sealed: False
```

Is Sealed

`Seal.is_sealed()`

Determine if Vault is sealed.

Returns True if Vault is seal, False otherwise.

Return type bool

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

print('Is Vault sealed: %s' % client.sys.is_sealed())
```

Example output:

```
Is Vault sealed: False
```

Read Seal Status

Seal.**read_seal_status**()

Read the seal status of the Vault.

This is an unauthenticated endpoint.

Supported methods: GET: /sys/seal-status. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

print('Is Vault sealed: %s' % client.sys.read_seal_status()['sealed'])
```

Example output:

```
Is Vault sealed: False
```

Seal

Seal.**seal**()

Seal the Vault.

In HA mode, only an active node can be sealed. Standby nodes should be restarted to get the same effect. Requires a token with root policy or sudo capability on the path.

Supported methods: PUT: /sys/seal. Produces: 204 (empty body)

Returns The response of the request.

Return type requests.Response

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.seal()
```

Submit Unseal Key

Seal.**submit_unseal_key** (*key=None, reset=False, migrate=False*)

Enter a single master key share to progress the unsealing of the Vault.

If the threshold number of master key shares is reached, Vault will attempt to unseal the Vault. Otherwise, this API must be called multiple times until that threshold is met.

Either the key or reset parameter must be provided; if both are provided, reset takes precedence.

Supported methods: PUT: /sys/unseal. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single master key share. This is required unless reset is true.
- **reset** (*bool*) – Specifies if previously-provided unseal keys are discarded and the unseal process is reset.
- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.submit_unseal_key(key=key)
```

Submit Unseal Keys

Seal.**submit_unseal_keys** (*keys, migrate=False*)

Enter multiple master key share to progress the unsealing of the Vault.

Parameters

- **keys** (*List[str]*) – List of master key shares.
- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the last unseal request.

Return type dict

Examples

```
import hvac
client = hvac.Client(url='https://127.0.0.1:8200')

client.sys.submit_unseal_keys(keys=keys)
```

2.3.12 Wrapping

- *Unwrap*
- *Is Sealed*

Unwrap

Is Sealed

Seal.**is_sealed**()

Determine if Vault is sealed.

Returns True if Vault is seal, False otherwise.

Return type bool

Examples

```
import hvac

client = hvac.Client(url='https://127.0.0.1:8200')
client.write(
    path="auth/approle-test/role/testrole",
)
result = client.write(
    path='auth/approle-test/role/testrole/secret-id',
    wrap_ttl="10s",
)

unwrap_response = client.sys.unwrap(
    token=result['wrap_info']['token'],
)
print('Unwrapped approle role token secret id accessor: "%s"' % unwrap_response['data
↪'] ['secret_id_accessor'])
```

Example output:

```
Unwrapped approle role token secret id accessor: "..."
```

2.4 Initialize and seal/unseal

```
print(client.sys.is_initialized()) # => False

shares = 5
threshold = 3

result = client.sys.initialize(shares, threshold)

root_token = result['root_token']
keys = result['keys']

print(client.sys.is_initialized()) # => True

print(client.sys.is_sealed()) # => True

# unseal with individual keys
client.sys.unseal(keys[0])
client.sys.unseal(keys[1])
client.sys.unseal(keys[2])

# unseal with multiple keys until threshold met
client.sys.unseal_multi(keys)

print(client.sys.is_sealed()) # => False

client.sys.seal()

print(client.sys.is_sealed()) # => True
```

- *Making Use of Private CA*
- *Custom Requests / HTTP Adapter*
- *Vault Agent Unix Socket Listener*

3.1 Making Use of Private CA

There is a not uncommon use case of people deploying Hashicorp Vault with a private certificate authority. Unfortunately the *requests* module does not make use of the system CA certificates. Instead of disabling SSL verification you can make use of the *REQUESTS_CA_BUNDLE* environment variable.

As documented in the advanced usage section for requests this environment variable should point to a file that is comprised of all CA certificates you may wish to use. This can be a single private CA, or an existing list of root certificates with the private appended to the end. The following example shows how to achieve this:

```
$ cp "$(python -c 'import certifi;print certifi.where();')" /tmp/bundle.pem
$ cat /path/to/custom.pem >> /tmp/bundle.pem
$ export REQUESTS_CA_BUNDLE=/tmp/bundle.pem
```

Alternative, this environmental variable can be set via the *os* module in-line with other Python statements. The following example would be one way to manage this configuration on a Ubuntu host:

```
import os

import hvac

def get_vault_client(vault_url=VAULT_URL, certs=VAULT_CERTS):
    """
```

(continues on next page)

(continued from previous page)

```

Instantiates a hvac / vault client.
:param vault_url: string, protocol + address + port for the vault service
:param certs: tuple, Optional tuple of self-signed certs to use for
↪verification
    with hvac's requests adapater.
:return: hvac.Client
"""
logger.debug('Retrieving a vault (hvac) client...')
if certs:
    # When use a self-signed certificate for the vault service itself, we
↪need to
    # include our local ca bundle here for the underlying requests module.
    os.environ['REQUESTS_CA_BUNDLE'] = '/etc/ssl/certs/ca-certificates.crt
↪'

vault_client = hvac.Client(
    url=vault_url,
    cert=certs,
)

vault_client.token = load_vault_token(vault_client)

if not vault_client.is_authenticated():
    error_msg = 'Unable to authenticate to the Vault service'
    raise hvac.exceptions.Unauthorized(error_msg)

return vault_client

```

3.2 Custom Requests / HTTP Adapter

New in version 0.6.2.

Calls to the `requests` module. (which provides the methods hvac utilizes to send HTTP/HTTPS request to Vault instances) were extracted from the `Client` class and moved to a newly added `hvac.adapters()` module. The `Client` class itself defaults to an instance of the `JSONAdapter` class for its `_adapter` private attribute attribute if no adapter argument is provided to its `constructor`. This attribute provides an avenue for modifying the manner in which hvac completes request. To enable this type of customization, implement a class of type `hvac.adapters.Adapter()`, override its abstract methods, and pass this custom class to the adapter argument of the `Client` constructor

3.3 Vault Agent Unix Socket Listener

hvac does not currently offer direct support of requests to a Vault agent process configured with a unix socket listener. However this use case can be handled with the help of the `requests_unixsocket` module. To accomplish this, first ensure the module is available (e.g. `pip install requests_unixsocket`), and then instantiate the `Client` class in the following manner:

```

import urllib.parse

import requests_unixsocket
import hvac

```

(continues on next page)

(continued from previous page)

```
vault_agent_socket_path = '/var/run/vault/agent.sock'
socket_url = 'http+unix://{encoded_path}'.format(
    encoded_path=urllib.parse.quote(vault_agent_socket_path, safe='')
)
socket_session = requests_unixsocket.Session()
client = hvac.Client(
    url=socket_url,
    session=socket_session,
)
print(client.secrets.kv.read_secret_version(path='some-secret'))
```


4.1 hvac.v1

```
class hvac.v1.Client (url=None, token=None, cert=None, verify=True, timeout=30, proxies=None, allow_redirects=True, session=None, adapter=<class 'hvac.adapters.JSONAdapter'>, namespace=None, **kwargs)
```

Bases: object

The hvac Client class for HashiCorp's Vault.

```
__init__ (url=None, token=None, cert=None, verify=True, timeout=30, proxies=None, allow_redirects=True, session=None, adapter=<class 'hvac.adapters.JSONAdapter'>, namespace=None, **kwargs)
```

Creates a new hvac client instance.

Parameters

- **url** (*str*) – Base URL for the Vault instance being addressed.
- **token** (*str*) – Authentication token to include in requests sent to Vault.
- **cert** (*tuple*) – Certificates for use in requests sent to the Vault instance. This should be a tuple with the certificate and then key.
- **verify** (*Union[bool, str]*) – Either a boolean to indicate whether TLS verification should be performed when sending requests to Vault, or a string pointing at the CA bundle to use for verification. See <http://docs.python-requests.org/en/master/user/advanced/#ssl-cert-verification>.
- **timeout** (*int*) – The timeout value for requests sent to Vault.
- **proxies** (*dict*) – Proxies to use when performing requests. See: <http://docs.python-requests.org/en/master/user/advanced/#proxies>
- **allow_redirects** (*bool*) – Whether to follow redirects when sending requests to Vault.

- **session** (*request.Session*) – Optional session object to use when performing request.
- **adapter** (*hvac.adapters.Adapter*) – Optional class to be used for performing requests. If none is provided, defaults to `hvac.adapters.JSONRequest`
- **kwargs** (*dict*) – Additional parameters to pass to the adapter constructor.
- **namespace** (*str*) – Optional Vault Namespace.

adapter

allow_redirects

audit_hash (*name, input*)

Call to deprecated function ‘audit_hash’. This method will be removed in version ‘0.9.0’ Please use the ‘calculate_hash’

Docstring content from this method’s replacement copied below: Hash the given input data with the specified audit device’s hash function and salt.

This endpoint can be used to discover whether a given plaintext string (the input parameter) appears in the audit log in obfuscated form.

Supported methods: POST: `/sys/audit-hash/{path}`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – The path of the audit device to generate hashes for. This is part of the request URL.
- **input_to_hash** (*str | unicode*) – The input string to hash.

Returns The JSON response of the request.

Return type `requests.Response`

auth

Accessor for the Client instance’s auth methods. Provided via the `hvac.api.AuthMethods` class.
:return: This Client instance’s associated Auth instance. :rtype: `hvac.api.AuthMethods`

auth_app_id (*app_id, user_id, mount_point='app-id', use_token=True*)

POST `/auth/<mount point>/login`

Parameters

- **app_id** –
- **user_id** –
- **mount_point** –
- **use_token** –

Returns

Return type

auth_approle (*role_id, secret_id=None, mount_point='approle', use_token=True*)

POST `/auth/<mount point>/login`

Parameters

- **role_id** –
- **secret_id** –
- **mount_point** –

- `use_token` –

Returns

Return type

`auth_aws_iam` (*access_key*, *secret_key*, *session_token=None*, *header_value=None*, *mount_point='aws'*, *role=""*, *use_token=True*, *region='us-east-1'*)

Call to deprecated function 'auth_aws_iam'. This method will be removed in version '0.11.2' Please use the 'iam_login' method.

Docstring content from this method's replacement copied below: Fetch a token

This endpoint verifies the pkcs7 signature of the instance identity document or the signature of the signed GetCallerIdentity request. With the ec2 auth method, or when inferring an EC2 instance, verifies that the instance is actually in a running state. Cross checks the constraints defined on the role with which the login is being performed. With the ec2 auth method, as an alternative to pkcs7 signature, the identity document along with its RSA digest can be supplied to this endpoint

Parameters `mount_point` –

Returns

`auth_cubbyhole` (*token*)

Perform a login request with a wrapped token.

Stores the unwrapped token in the resulting Vault response for use by the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.

Parameters `token` (*str | unicode*) – Wrapped token

Returns The (JSON decoded) response of the auth request

Return type dict

`auth_ec2` (*pkcs7*, *nonce=None*, *role=None*, *use_token=True*, *mount_point='aws-ec2'*)

Call to deprecated function 'auth_ec2'. This method will be removed in version '0.11.2' Please use the 'ec2_login' method.

Docstring content from this method's replacement copied below: Fetch a token

Parameters

- `pkcs7` –
- `nonce` –
- `role` –
- `use_token` –
- `mount_point` –

`auth_gcp` (**args*, ***kwargs*)

Call to deprecated function 'auth_gcp'. This method will be removed in version '0.9.0' Please use the 'login' method.

Docstring content from this method's replacement copied below: Login to retrieve a Vault token via the GCP auth method.

This endpoint takes a signed JSON Web Token (JWT) and a role name for some entity. It verifies the JWT signature with Google Cloud to authenticate that entity and then authorizes the entity for the given role.

Supported methods: POST: `/auth/{mount_point}/login`. Produces: 200 application/json

Parameters

- **role** (*str* | *unicode*) – The name of the role against which the login is being attempted.
- **jwt** (*str* | *unicode*) – A signed JSON web token
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the *hvac.adapters.Adapter()* instance under the *_adapater* Client attribute.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

auth_github (**args*, ***kwargs*)

Call to deprecated function ‘auth_github’. This method will be removed in version ‘0.8.0’ Please use the ‘login’ method

Docstring content from this method’s replacement copied below: Login using GitHub access token.

Supported methods: POST: /auth/{mount_point}/login. Produces: 200 application/json

Parameters

- **token** (*str* | *unicode*) – GitHub personal API token.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the *hvac.adapters.Adapter()* instance under the *_adapater* Client attribute.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the login request.

Return type dict

auth_kubernetes (*role*, *jwt*, *use_token=True*, *mount_point='kubernetes'*)

POST /auth/<mount_point>/login

Parameters

- **role** (*str.*) – Name of the role against which the login is being attempted.
- **jwt** (*str.*) – Signed JSON Web Token (JWT) for authenticating a service account.
- **use_token** (*bool.*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the current Client class instance.
- **mount_point** (*str.*) – The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Parsed JSON response from the config POST request.

Return type dict.

auth_ldap (**args*, ***kwargs*)

Call to deprecated function ‘auth_ldap’. This method will be removed in version ‘0.8.0’ Please use the ‘login’ method

Docstring content from this method’s replacement copied below:

Log in with LDAP credentials.

Supported methods: POST: /auth/{mount_point}/login/{username}. Produces: 200 application/json

Parameters

- **username** (*str* | *unicode*) – The username of the LDAP user
- **password** (*str* | *unicode*) – The password for the LDAP user
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the `login_with_user` request.

Return type `requests.Response`

auth_tls (*mount_point='cert', use_token=True*)
POST /auth/<mount point>/login

Parameters

- **mount_point** –
- **use_token** –

Returns

Return type

auth_userpass (*username, password, mount_point='userpass', use_token=True, **kwargs*)
POST /auth/<mount point>/login/<username>

Parameters

- **username** –
- **password** –
- **mount_point** –
- **use_token** –
- **kwargs** –

Returns

Return type

cancel_generate_root ()

Call to deprecated function ‘cancel_generate_root’. This method will be removed in version ‘0.9.0’ Please use the ‘cancel_rekey’.
Docstring content from this method’s replacement copied below: Cancel any in-progress root generation attempt.

This clears any progress made. This must be called to change the OTP or PGP key being used.

Supported methods: DELETE: /sys/generate-root/attempt. Produces: 204 (empty body)

Returns The response of the request.

Return type `request.Response`

cancel_rekey ()

Call to deprecated function ‘cancel_rekey’. This method will be removed in version ‘0.9.0’ Please use the ‘cancel_rekey’.
Docstring content from this method’s replacement copied below: Cancel any in-progress rekey.

This clears the rekey settings as well as any progress made. This must be called to change the parameters of the rekey.

Note: Verification is still a part of a rekey. If rekeying is canceled during the verification flow, the current unseal keys remain valid.

Supported methods: DELETE: /sys/rekey/init. Produces: 204 (empty body) DELETE: /sys/rekey-recovery-key/init. Produces: 204 (empty body)

Parameters `recovery_key` (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The response of the request.

Return type requests.Response

close ()

Call to deprecated function ‘close’. This method will be removed in version ‘0.8.0’ Please use the ‘close’ method on the ‘hvac.adapters’ class moving forward. Docstring content from this method’s replacement copied below: Close the underlying Requests session.

create_app_id (*app_id*, *policies*, *display_name=None*, *mount_point='app-id'*, ***kwargs*)

POST /auth/<mount point>/map/app-id/<app_id>

Parameters

- `app_id` –
- `policies` –
- `display_name` –
- `mount_point` –
- `kwargs` –

Returns

Return type

create_ec2_role (*role*, *bound_ami_id=None*, *bound_account_id=None*, *bound_iam_role_arn=None*, *bound_iam_instance_profile_arn=None*, *bound_ec2_instance_id=None*, *bound_region=None*, *bound_vpc_id=None*, *bound_subnet_id=None*, *role_tag=None*, *ttl=None*, *max_ttl=None*, *period=None*, *policies=None*, *allow_instance_migration=False*, *disallow_reauthentication=False*, *resolve_aws_unique_ids=None*, *mount_point='aws-ec2'*)

Call to deprecated function ‘create_ec2_role’. This method will be removed in version ‘0.11.2’ Please use the ‘create_

Docstring content from this method’s replacement copied below: Registers a role in the method. Only those instances or principals which are using the role registered

using this endpoint, will be able to perform the login operation

Constraints can be specified on the role, that are applied on the instances or principals attempting to login. At least one constraint must be specified on the role. The available constraints you can choose are dependent on the `auth_type` of the role and, if the `auth_type` is `iam`, then whether inferencing is enabled. A role will not let you configure a constraint if it is not checked by the `auth_type` and inferencing configuration of that role. For the constraints which accept a list of values, the authenticating instance/principal must match any one value in the list in order to satisfy that constraint

Parameters

- `role` –
- `auth_type` –
- `bound_ami_id` –
- `bound_account_id` –
- `bound_region` –
- `bound_vpc_id` –
- `bound_subnet_id` –
- `bound_iam_role_arn` –
- `bound_iam_instance_profile_arn` –
- `bound_ec2_instance_id` –
- `role_tag` –
- `bound_iam_principal_arn` –
- `inferred_entity_type` –
- `inferred_aws_region` –
- `resolve_aws_unique_ids` –
- `ttl` –
- `max_ttl` –
- `period` –
- `policies` –
- `allow_instance_migration` –
- `disallow_reauthentication` –
- `mount_point` –

Returns

`create_ec2_role_tag` (*role*, *policies=None*, *max_ttl=None*, *instance_id=None*, *disallow_reauthentication=False*, *allow_instance_migration=False*, *mount_point='aws-ec2'*)

Call to deprecated function ‘create_ec2_role_tag’. This method will be removed in version ‘0.11.2’. Please use the ‘cr

Docstring content from this method’s replacement copied below: Creates a role tag on the role, which helps in restricting the capabilities that are set on the role.

Role tags are not tied to any specific ec2 instance unless specified explicitly using the `instance_id` parameter

Role tags are not tied to any specific ec2 instance unless specified explicitly using the `instance_id` parameter. By default, role tags are designed to be used across all instances that satisfies the constraints on the role. Regardless of which instances have role tags on them, capabilities defined in a role tag must be a strict subset of the given role’s capabilities. Note that, since adding and removing a tag is often a widely distributed privilege, care needs to be taken to ensure that the instances are attached with correct tags to not let them gain more privileges than what were intended. If a role tag is changed, the capabilities inherited by the instance will be those defined on the new role tag. Since those must be a subset of the role capabilities, the role should never provide more capabilities than any given instance can be allowed to gain in a worst-case scenario

Parameters

- **role** –
- **policies** –
- **max_ttl** –
- **instance_id** –
- **allow_instance_migration** –
- **disallow_reauthentication** –
- **mount_point** –

Returns

create_kubernetes_configuration (*kubernetes_host*, *kubernetes_ca_cert=None*,
token_reviewer_jwt=None, *pem_keys=None*,
mount_point='kubernetes')

POST /auth/<mount_point>/config

Parameters

- **kubernetes_host** (*str.*) – A host:port pair, or a URL to the base of the Kubernetes API server.
- **kubernetes_ca_cert** (*str.*) – PEM encoded CA cert for use by the TLS client used to talk with the Kubernetes API.
- **token_reviewer_jwt** (*str.*) – A service account JWT used to access the TokenReview API to validate other JWTs during login. If not set the JWT used for login will be used to access the API.
- **pem_keys** (*list.*) – Optional list of PEM-formated public keys or certificates used to verify the signatures of Kubernetes service account JWTs. If a certificate is given, its public key will be extracted. Not every installation of Kubernetes exposes these keys.
- **mount_point** (*str.*) – The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Will be an empty body with a 204 status code upon success

Return type requests.Response.

create_kubernetes_role (*name*, *bound_service_account_names*,
bound_service_account_namespaces, *ttl=""*, *max_ttl=""*, *period=""*,
policies=None, *mount_point='kubernetes'*)

POST /auth/<mount_point>/role/:name

Parameters

- **name** (*str.*) – Name of the role.
- **bound_service_account_names** (*list.*) – List of service account names able to access this role. If set to “*” all names are allowed, both this and *bound_service_account_namespaces* can not be “*”.
- **bound_service_account_namespaces** (*list.*) – List of namespaces allowed to access this role. If set to “*” all namespaces are allowed, both this and *bound_service_account_names* can not be set to “*”.
- **ttl** (*str.*) – The TTL period of tokens issued using this role in seconds.

- **max_ttl** (*str.*) – The maximum allowed lifetime of tokens issued in seconds using this role.
- **period** (*str.*) – If set, indicates that the token generated using this role should never expire. The token should be renewed within the duration specified by this value. At each renewal, the token’s TTL will be set to the value of this parameter.
- **policies** (*list.*) – Policies to be set on tokens issued using this role
- **mount_point** (*str.*) – The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Will be an empty body with a 204 status code upon success

Return type requests.Response.

create_role (*role_name, mount_point='appprole', **kwargs*)
POST /auth/<mount_point>/role/<role name>

Parameters

- **role_name** –
- **mount_point** –
- **kwargs** –

Returns

Return type

create_role_custom_secret_id (*role_name, secret_id, meta=None, mount_point='appprole'*)
POST /auth/<mount_point>/role/<role name>/custom-secret-id

Parameters

- **role_name** –
- **secret_id** –
- **meta** –
- **mount_point** –

Returns

Return type

create_role_secret_id (*role_name, meta=None, cidr_list=None, wrap_ttl=None, mount_point='appprole'*)
POST /auth/<mount_point>/role/<role name>/secret-id

Parameters

- **role_name** –
- **meta** –
- **cidr_list** –
- **wrap_ttl** –
- **mount_point** –

Returns

Return type

create_token (*role=None, token_id=None, policies=None, meta=None, no_parent=False, lease=None, display_name=None, num_uses=None, no_default_policy=False, ttl=None, orphan=False, wrap_ttl=None, renewable=None, explicit_max_ttl=None, period=None, token_type=None*)

POST /auth/token/create

POST /auth/token/create/<role>

POST /auth/token/create-orphan

Parameters

- **role** -
- **token_id** -
- **policies** -
- **meta** -
- **no_parent** -
- **lease** -
- **display_name** -
- **num_uses** -
- **no_default_policy** -
- **ttl** -
- **orphan** -
- **wrap_ttl** -
- **renewable** -
- **explicit_max_ttl** -
- **period** -
- **token_type** -

Returns

Return type

create_token_role (*role, allowed_policies=None, disallowed_policies=None, orphan=None, period=None, renewable=None, path_suffix=None, explicit_max_ttl=None*)

POST /auth/token/roles/<role>

Parameters

- **role** -
- **allowed_policies** -
- **disallowed_policies** -
- **orphan** -
- **period** -
- **renewable** -
- **path_suffix** -
- **explicit_max_ttl** -

Returns**Return type**

create_user_id (*user_id*, *app_id*, *cidr_block=None*, *mount_point='app-id'*, ***kwargs*)
 POST /auth/<mount point>/map/user-id/<user_id>

Parameters

- **user_id** –
- **app_id** –
- **cidr_block** –
- **mount_point** –
- **kwargs** –

Returns**Return type**

create_userpass (*username*, *password*, *policies*, *mount_point='userpass'*, ***kwargs*)
 POST /auth/<mount point>/users/<username>

Parameters

- **username** –
- **password** –
- **policies** –
- **mount_point** –
- **kwargs** –

Returns**Return type**

create_vault_ec2_certificate_configuration (*cert_name*, *aws_public_cert*,
mount_point='aws-ec2')

Call to deprecated function ‘create_vault_ec2_certificate_configuration’. This method will be removed in version ‘0.10.0’.

Docstring content from this method’s replacement copied below: Registers an AWS public key to be used to verify the instance identity documents

While the PKCS#7 signature of the identity documents have DSA digest, the identity signature will have RSA digest, and hence the public keys for each type varies respectively. Indicate the type of the public key using the “type” parameter

Supported methods: POST: /auth/{mount_point}/config/certificate/:cert_name Produces: 204 (empty body)

Parameters

- **cert_name** (*string | unicode*) – Name of the certificate
- **aws_public_cert** – Base64 encoded AWS Public key required to verify PKCS7 signature of the EC2 instance metadata
- **document_type** (*string | unicode*) – Takes the value of either “pkcs7” or “identity”, indicating the type of document which can be verified using the given certificate
- **mount_point** (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request

Return type request.Response

create_vault_ec2_client_configuration (*access_key*, *secret_key*, *endpoint=None*,
mount_point='aws-ec2')

Call to deprecated function ‘create_vault_ec2_client_configuration’. This method will be removed in version ‘0.11.2’

Docstring content from this method’s replacement copied below: Configures the credentials required to perform API calls to AWS as well as custom endpoints to talk to AWS

API

The instance identity document fetched from the PKCS#7 signature will provide the EC2 instance ID. The credentials configured using this endpoint will be used to query the status of the instances via DescribeInstances API. If static credentials are not provided using this endpoint, then the credentials will be retrieved from the environment variables AWS_ACCESS_KEY, AWS_SECRET_KEY and AWS_REGION respectively. If the credentials are still not found and if the method is configured on an EC2 instance with metadata querying capabilities, the credentials are fetched automatically

Supported methods: POST: /auth/{mount_point}/config Produces: 204 (empty body)

Parameters

- **max_retries** (*int*) – Number of max retries the client should use for recoverable errors. The default (-1) falls back to the AWS SDK’s default behavior
- **access_key** (*str | unicode*) – AWS Access key with permissions to query AWS APIs. The permissions required depend on the specific configurations. If using the iam auth method without inferencing, then no credentials are necessary. If using the ec2 auth method or using the iam auth method with inferencing, then these credentials need access to ec2:DescribeInstances. If additionally a bound_iam_role is specified, then these credentials also need access to iam:GetInstanceProfile. If, however, an alternate sts configuration is set for the target account, then the credentials must be permissioned to call sts:AssumeRole on the configured role, and that role must have the permissions described here
- **secret_key** (*str | unicode*) – AWS Secret key with permissions to query AWS APIs
- **endpoint** (*str | unicode*) – URL to override the default generated endpoint for making AWS EC2 API calls
- **iam_endpoint** (*str | unicode*) – URL to override the default generated endpoint for making AWS IAM API calls
- **sts_endpoint** (*str | unicode*) – URL to override the default generated endpoint for making AWS STS API calls
- **iam_server_id_header_value** (*str | unicode*) – The value to require in the X-Vault-AWS-IAM-Server-ID header as part of GetCallerIdentity requests that are used in the iam auth method. If not set, then no value is required or validated. If set, clients must include an X-Vault-AWS-IAM-Server-ID header in the headers of login requests, and further this header must be among the signed headers validated by AWS. This is to protect against different types of replay attacks, for example a signed request sent to a dev server being resent to a production server
- **mount_point** (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request.

Return type requests.Response

delete (*path*)

DELETE /<path>

Parameters *path* –

Returns

Return type

delete_app_id (*app_id*, *mount_point*='app-id')

DELETE /auth/<mount_point>/map/app-id/<app_id>

Parameters

- *app_id* –
- *mount_point* –

Returns

Return type

delete_ec2_role (*role*, *mount_point*='aws-ec2')

Call to deprecated function ‘delete_ec2_role’. This method will be removed in version ‘0.11.2’ Please use the ‘delete_

Docstring content from this method’s replacement copied below: Deletes the previously registered role

Parameters

- *role* –
- *mount_point* –

Returns

delete_kubernetes_role (*role*, *mount_point*='kubernetes')

DELETE /auth/<mount_point>/role/:role

Parameters

- *role* (*Name of the role.*)–str.
- *mount_point* (*str.*)– The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Will be an empty body with a 204 status code upon success.

Return type requests.Response.

delete_policy (*name*)

Call to deprecated function ‘delete_policy’. This method will be removed in version ‘0.9.0’ Please use the ‘delete_policy

Docstring content from this method’s replacement copied below: Delete the policy with the given name.

This will immediately affect all users associated with this policy.

Supported methods: DELETE: /sys/policy/{name}. Produces: 204 (empty body)

Parameters *name* (*str | unicode*)– Specifies the name of the policy to delete.

Returns The response of the request.

Return type requests.Response

delete_role (*role_name*, *mount_point='approle'*)
DELETE /auth/<mount_point>/role/<role name>

Parameters

- **role_name** –
- **mount_point** –

Returns

Return type

delete_role_secret_id (*role_name*, *secret_id*, *mount_point='approle'*)
POST /auth/<mount_point>/role/<role name>/secret-id/destroy

Parameters

- **role_name** –
- **secret_id** –
- **mount_point** –

Returns

Return type

delete_role_secret_id_accessor (*role_name*, *secret_id_accessor*, *mount_point='approle'*)
POST /auth/<mount_point>/role/<role name>/secret-id-accessor/destroy

Parameters

- **role_name** –
- **secret_id_accessor** –
- **mount_point** –

Returns

Return type

delete_token_role (*role*)
Deletes the named token role.

Parameters **role** –

Returns

Return type

delete_user_id (*user_id*, *mount_point='app-id'*)
DELETE /auth/<mount_point>/map/user-id/<user_id>

Parameters

- **user_id** –
- **mount_point** –

Returns

Return type

delete_userpass (*username*, *mount_point='userpass'*)
DELETE /auth/<mount point>/users/<username>

Parameters

- `username` –
- `mount_point` –

Returns

Return type

`delete_vault_ec2_client_configuration` (*mount_point='aws-ec2'*)

Call to deprecated function ‘delete_vault_ec2_client_configuration’. This method will be removed in version ‘0.11.2’

Docstring content from this method’s replacement copied below: Deletes the previously configured AWS access credentials

Supported methods: DELETE: /auth/{mount_point}/config Produces: 204 (empty body)

Parameters `mount_point` (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request.

Return type requests.Response

`disable_audit_backend` (*name*)

Call to deprecated function ‘disable_audit_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘

Docstring content from this method’s replacement copied below: Disable the audit device at the given path.

Supported methods: DELETE: /sys/audit/{path}. Produces: 204 (empty body)

Parameters `path` (*str | unicode*) – The path of the audit device to delete. This is part of the request URL.

Returns The response of the request.

Return type requests.Response

`disable_auth_backend` (*mount_point*)

Call to deprecated function ‘disable_auth_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘d

Docstring content from this method’s replacement copied below: Disable the auth method at the given auth path.

Supported methods: DELETE: /sys/auth/{path}. Produces: 204 (empty body)

Parameters `path` (*str | unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.

Returns The response of the request.

Return type requests.Response

`disable_secret_backend` (*mount_point*)

Call to deprecated function ‘disable_secret_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘

Docstring content from this method’s replacement copied below: Disable the mount point specified by the provided path.

Supported methods: DELETE: /sys/mounts/{path}. Produces: 204 (empty body)

Parameters `path` (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.

Returns The response of the request.

Return type requests.Response

enable_audit_backend (*backend_type*, *description=None*, *options=None*, *name=None*)

Call to deprecated function ‘enable_audit_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘en

Docstring content from this method’s replacement copied below: Enable a new audit device at the supplied path.

The path can be a single word name or a more complex, nested path.

Supported methods: PUT: /sys/audit/{path}. Produces: 204 (empty body)

Parameters

- **device_type** (*str* | *unicode*) – Specifies the type of the audit device.
- **description** (*str* | *unicode*) – Human-friendly description of the audit device.
- **options** (*str* | *unicode*) – Configuration options to pass to the audit device itself. This is dependent on the audit device type.
- **path** (*str* | *unicode*) – Specifies the path in which to enable the audit device. This is part of the request URL.
- **local** (*bool*) – Specifies if the audit device is a local only.

Returns The response of the request.

Return type requests.Response

enable_auth_backend (*backend_type*, *description=None*, *mount_point=None*, *config=None*, *plugin_name=None*)

Call to deprecated function ‘enable_auth_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘en

Docstring content from this method’s replacement copied below: Enable a new auth method.

After enabling, the auth method can be accessed and configured via the auth path specified as part of the URL. This auth path will be nested under the auth prefix.

Supported methods: POST: /sys/auth/{path}. Produces: 204 (empty body)

Parameters

- **method_type** (*str* | *unicode*) – The name of the authentication method type, such as “github” or “token”.
- **description** (*str* | *unicode*) – A human-friendly description of the auth method.
- **config** (*dict*) – Configuration options for this auth method. These are the possible values:
 - **default_lease_ttl**: The default lease duration, specified as a string duration like “5s” or “30m”.
 - **max_lease_ttl**: The maximum lease duration, specified as a string duration like “5s” or “30m”.
 - **audit_non_hmac_request_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the request data object.
 - **audit_non_hmac_response_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the response data object.

- **listing_visibility**: Specifies whether to show this mount in the UI-specific listing endpoint.
- **passthrough_request_headers**: Comma-separated list of headers to whitelist and pass from the request to the backend.
- **plugin_name** (*str | unicode*) – The name of the auth plugin to use based from the name in the plugin catalog. Applies only to plugin methods.
- **local** (*bool*) – <Vault enterprise only> Specifies if the auth method is a local only. Local auth methods are not replicated nor (if a secondary) removed by replication.
- **path** (*str | unicode*) – The path to mount the method on. If not provided, defaults to the value of the “method_type” argument.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

enable_secret_backend (*backend_type, description=None, mount_point=None, config=None, options=None*)

Call to deprecated function ‘enable_secret_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘

Docstring content from this method’s replacement copied below: Enable a new secrets engine at the given path.

Supported methods: POST: /sys/mounts/{path}. Produces: 204 (empty body)

Parameters

- **backend_type** (*str | unicode*) – The name of the backend type, such as “github” or “token”.
- **path** (*str | unicode*) – The path to mount the method on. If not provided, defaults to the value of the “method_type” argument.
- **description** (*str | unicode*) – A human-friendly description of the mount.
- **config** (*dict*) – Configuration options for this mount. These are the possible values:
 - **default_lease_ttl**: The default lease duration, specified as a string duration like “5s” or “30m”.
 - **max_lease_ttl**: The maximum lease duration, specified as a string duration like “5s” or “30m”.
 - **force_no_cache**: Disable caching.
 - **plugin_name**: The name of the plugin in the plugin catalog to use.
 - **audit_non_hmac_request_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the request data object.
 - **audit_non_hmac_response_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the response data object.
 - **listing_visibility**: Specifies whether to show this mount in the UI-specific listing endpoint. (“unauth” or “hidden”)
 - **passthrough_request_headers**: Comma-separated list of headers to whitelist and pass from the request to the backend.

- **options** (*dict*) – Specifies mount type specific options that are passed to the backend.
 - **version**: <KV> The version of the KV to mount. Set to “2” for mount KV v2.
- **plugin_name** (*str | unicode*) – Specifies the name of the plugin to use based from the name in the plugin catalog. Applies only to plugin backends.
- **local** (*bool*) – <Vault enterprise only> Specifies if the auth method is a local only. Local auth methods are not replicated nor (if a secondary) removed by replication.
- **seal_wrap** (*bool*) – <Vault enterprise only> Enable seal wrapping for the mount.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

generate_root (*key, nonce*)

Call to deprecated function ‘generate_root’. This method will be removed in version ‘0.9.0’ Please use the ‘generate_

Docstring content from this method’s replacement copied below: Enter a single master key share to progress the root generation attempt.

If the threshold number of master key shares is reached, Vault will complete the root generation and issue the new token. Otherwise, this API must be called multiple times until that threshold is met. The attempt nonce must be provided with each call.

Supported methods: PUT: /sys/generate-root/update. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single master key share.
- **nonce** (*str | unicode*) – The nonce of the attempt.

Returns The JSON response of the request.

Return type dict

generate_root_status

get_app_id (*app_id, mount_point='app-id', wrap_ttl=None*)

GET /auth/<mount_point>/map/app-id/<app_id>

Parameters

- **app_id** –
- **mount_point** –
- **wrap_ttl** –

Returns

Return type

get_auth_backend_tuning (*backend_type, mount_point=None*)

Call to deprecated function ‘get_auth_backend_tuning’. This method will be removed in version ‘0.9.0’ Please use th

Docstring content from this method’s replacement copied below: Read the given auth path’s configuration.

This endpoint requires sudo capability on the final path, but the same functionality can be achieved without sudo via sys/mounts/auth/[auth-path]/tune.

Supported methods: GET: /sys/auth/{path}/tune. Produces: 200 application/json

Parameters `path` (*str* | *unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.

Returns The JSON response of the request.

Return type dict

`get_backed_up_keys ()`

Call to deprecated function ‘get_backed_up_keys’. This method will be removed in version ‘0.9.0’ Please use the ‘rekey’

Docstring content from this method’s replacement copied below: Retrieve the backup copy of PGP-encrypted unseal keys.

The returned value is the nonce of the rekey operation and a map of PGP key fingerprint to hex-encoded PGP-encrypted key.

Supported methods: PUT: /sys/rekey/backup. Produces: 200 application/json PUT: /sys/rekey-recovery-key/backup. Produces: 200 application/json

Parameters `recovery_key` (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type dict

`get_ec2_role (role, mount_point='aws-ec2')`

Call to deprecated function ‘get_ec2_role’. This method will be removed in version ‘0.11.2’ Please use the ‘read_role’

Docstring content from this method’s replacement copied below: Returns the previously registered role configuration

Parameters

- `role` –
- `mount_point` –

Returns

`get_kubernetes_configuration (mount_point='kubernetes')`

GET /auth/<mount_point>/config

Parameters `mount_point` (*str.*) – The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Parsed JSON response from the config GET request

Return type dict.

`get_kubernetes_role (name, mount_point='kubernetes')`

GET /auth/<mount_point>/role/:name

Parameters

- `name` (*str.*) – Name of the role.
- `mount_point` (*str.*) – The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Parsed JSON response from the read role GET request

Return type dict.

get_policy (*name*, *parse=False*)

Retrieve the policy body for the named policy.

Parameters

- **name** (*str* | *unicode*) – The name of the policy to retrieve.
- **parse** (*bool*) – Specifies whether to parse the policy body using pyhcl or not.

Returns The (optionally parsed) policy body for the specified policy.

Return type str | dict

get_role (*role_name*, *mount_point='aprole'*)

GET /auth/<mount_point>/role/<role name>

Parameters

- **role_name** –
- **mount_point** –

Returns

Return type

get_role_id (*role_name*, *mount_point='aprole'*)

GET /auth/<mount_point>/role/<role name>/role-id

Parameters

- **role_name** –
- **mount_point** –

Returns

Return type

get_role_secret_id (*role_name*, *secret_id*, *mount_point='aprole'*)

POST /auth/<mount_point>/role/<role name>/secret-id/lookup

Parameters

- **role_name** –
- **secret_id** –
- **mount_point** –

Returns

Return type

get_role_secret_id_accessor (*role_name*, *secret_id_accessor*, *mount_point='aprole'*)

POST /auth/<mount_point>/role/<role name>/secret-id-accessor/lookup

Parameters

- **role_name** –
- **secret_id_accessor** –
- **mount_point** –

Returns

Return type

`get_secret_backend_tuning` (*backend_type*, *mount_point=None*)

Call to deprecated function ‘get_secret_backend_tuning’. This method will be removed in version ‘0.9.0’ Please use t

Docstring content from this method’s replacement copied below: Read the given mount’s configuration.

Unlike the mounts endpoint, this will return the current time in seconds for each TTL, which may be the system default or a mount-specific value.

Supported methods: GET: /sys/mounts/{path}/tune. Produces: 200 application/json

Parameters `path` (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.

Returns The JSON response of the request.

Return type requests.Response

`get_user_id` (*user_id*, *mount_point='app-id'*, *wrap_ttl=None*)

GET /auth/<mount_point>/map/user-id/<user_id>

Parameters

- `user_id` –
- `mount_point` –
- `wrap_ttl` –

Returns

Return type

`get_vault_ec2_certificate_configuration` (*cert_name*, *mount_point='aws-ec2'*)

Call to deprecated function ‘get_vault_ec2_certificate_configuration’. This method will be removed in version ‘0.11.2

Docstring content from this method’s replacement copied below: Returns the previously configured AWS public key

Supported methods: GET: /v1/auth/{mount_point}/config/certificate/:cert_name Produces: 200 application/json

Parameters

- `cert_name` (*str | unicode*) – Name of the certificate
- `mount_point` – The “path” the aws auth method was mounted on

Returns The data key from the JSON response of the request.

Return type dict

`get_vault_ec2_client_configuration` (*mount_point='aws-ec2'*)

Call to deprecated function ‘get_vault_ec2_client_configuration’. This method will be removed in version ‘0.11.2’ Pl

Docstring content from this method’s replacement copied below: Returns the previously configured AWS access credentials

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The data key from the JSON response of the request.

Return type dict

ha_status

Read the high availability status and current leader instance of Vault.

Returns The JSON response returned by read_leader_status()

Return type dict

initialize (*secret_shares=5, secret_threshold=3, pgp_keys=None*)

Call to deprecated function ‘initialize’. This method will be removed in version ‘0.9.0’ Please use the ‘initialize’ meth

Docstring content from this method’s replacement copied below: Initialize a new Vault.

The Vault must not have been previously initialized. The recovery options, as well as the stored shares option, are only available when using Vault HSM.

Supported methods: PUT: /sys/init. Produces: 200 application/json

Parameters

- **secret_shares** (*int*) – The number of shares to split the master key into.
- **secret_threshold** (*int*) – Specifies the number of shares required to reconstruct the master key. This must be less than or equal secret_shares. If using Vault HSM with auto-unsealing, this value must be the same as secret_shares.
- **pgp_keys** (*list*) – List of PGP public keys used to encrypt the output unseal keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as secret_shares.
- **root_token_pgp_key** (*str | unicode*) – Specifies a PGP public key used to encrypt the initial root token. The key must be base64-encoded from its original binary representation.
- **stored_shares** (*int*) – <enterprise only> Specifies the number of shares that should be encrypted by the HSM and stored for auto-unsealing. Currently must be the same as secret_shares.
- **recovery_shares** (*int*) – <enterprise only> Specifies the number of shares to split the recovery key into.
- **recovery_threshold** (*int*) – <enterprise only> Specifies the number of shares required to reconstruct the recovery key. This must be less than or equal to recovery_shares.
- **recovery_pgp_keys** (*list*) – <enterprise only> Specifies an array of PGP public keys used to encrypt the output recovery keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as recovery_shares.

Returns The JSON response of the request.

Return type dict

is_authenticated ()

Helper method which returns the authentication status of the client

Returns

Return type

is_initialized ()

Call to deprecated function ‘is_initialized’. This method will be removed in version ‘0.9.0’ Please use the ‘is_initialized’ method.
 Docstring content from this method’s replacement copied below: Determine if Vault is initialized or not.

Returns True if Vault is initialized, False otherwise.

Return type bool

is_sealed()

Call to deprecated function ‘is_sealed’. This method will be removed in version ‘0.9.0’ Please use the ‘is_sealed’ method.
 Docstring content from this method’s replacement copied below: Determine if Vault is sealed.

Returns True if Vault is seal, False otherwise.

Return type bool

key_status

GET /sys/key-status

Returns Information about the current encryption key used by Vault.

Return type dict

list(path)

GET /<path>?list=true

Parameters path –

Returns

Return type

list_audit_backends()

Call to deprecated function ‘list_audit_backends’. This method will be removed in version ‘0.9.0’ Please use the ‘list_audit_backends’ method.
 Docstring content from this method’s replacement copied below: List enabled audit devices.

It does not list all available audit devices. This endpoint requires sudo capability in addition to any path-specific capabilities.

Supported methods: GET: /sys/audit. Produces: 200 application/json

Returns JSON response of the request.

Return type dict

list_auth_backends()

Call to deprecated function ‘list_auth_backends’. This method will be removed in version ‘0.9.0’ Please use the ‘list_auth_backends’ method.
 Docstring content from this method’s replacement copied below: List all enabled auth methods.

Supported methods: GET: /sys/auth. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

list_ec2_roles(mount_point='aws-ec2')

Call to deprecated function ‘list_ec2_roles’. This method will be removed in version ‘0.11.2’ Please use the ‘list_roles’ method.
 Docstring content from this method’s replacement copied below: Lists all the roles that are registered with the method

Parameters `mount_point` –

Returns

`list_kubernetes_roles` (*mount_point='kubernetes'*)

GET /auth/<mount_point>/role?list=true

Parameters `mount_point` (*str.*) – The “path” the k8s auth backend was mounted on. Vault currently defaults to “kubernetes”.

Returns Parsed JSON response from the list roles GET request.

Return type dict.

`list_policies` ()

Call to deprecated function ‘list_policies’. This method will be removed in version ‘0.9.0’ Please use the ‘list_policies

Docstring content from this method’s replacement copied below: List all configured policies.

Supported methods: GET: /sys/policy. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

`list_role_secrets` (*role_name, mount_point='aprole'*)

LIST /auth/<mount_point>/role/<role name>/secret-id

Parameters

- **role_name** (*str/unicode*) – Name of the AppRole.
- **mount_point** (*str/unicode*) – The “path” the AppRole auth backend was mounted on. Vault currently defaults to “aprole”.

Returns The JSON response of the request.

Return type dict

`list_roles` (*mount_point='aprole'*)

GET /auth/<mount_point>/role

Parameters `mount_point` –

Returns

Return type

`list_secret_backends` ()

Call to deprecated function ‘list_secret_backends’. This method will be removed in version ‘0.9.0’ Please use the ‘list

Docstring content from this method’s replacement copied below: Lists all the mounted secrets engines.

Supported methods: POST: /sys/mounts. Produces: 200 application/json

Returns JSON response of the request.

Return type dict

`list_token_roles` ()

GET /auth/token/roles?list=true

Returns

Return type

list_userpass (*mount_point='userpass'*)
GET /auth/<mount point>/users?list=true

Parameters *mount_point* –

Returns**Return type**

list_vault_ec2_certificate_configurations (*mount_point='aws-ec2'*)

Call to deprecated function ‘list_vault_ec2_certificate_configurations’. This method will be removed in version ‘0.11.’

Docstring content from this method’s replacement copied below: Lists all the AWS public certificates that are registered with the method

Supported methods LIST: /auth/{mount_point}/config/certificates Produces: 200 application/json

Parameters *mount_point* –

Returns

login (*url, use_token=True, **kwargs*)
Perform a login request.

Associated request is typically to a path prefixed with “/v1/auth”) and optionally stores the client token sent in the resulting Vault response for use by the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.

Parameters

- **url** (*str | unicode*) – Path to send the authentication request to.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the params sent with the request.

Returns The response of the auth request.

Return type requests.Response

logout (*revoke_token=False*)
Clears the token used for authentication, optionally revoking it before doing so.

Parameters *revoke_token* –

Returns**Return type**

lookup_token (*token=None, accessor=False, wrap_ttl=None*)
GET /auth/token/lookup/<token>
GET /auth/token/lookup-accessor/<token-accessor>
GET /auth/token/lookup-self

Parameters

- **token** (*str.*) –

- **accessor** (*str.*) –

- **wrap_ttl** (*int.*) –

Returns

Return type

read (*path, wrap_ttl=None*)

GET /<path>

Parameters

- **path** –

- **wrap_ttl** –

Returns

Return type

read_lease (*lease_id*)

Call to deprecated function ‘read_lease’. This method will be removed in version ‘0.9.0’ Please use the ‘read_lease’ method on

Docstring content from this method’s replacement copied below: Retrieve lease metadata.

Supported methods: PUT: /sys/leases/lookup. Produces: 200 application/json

Parameters **lease_id** (*str | unicode*) – the ID of the lease to lookup.

Returns Parsed JSON response from the leases PUT request

Return type dict.

read_userpass (*username, mount_point='userpass'*)

GET /auth/<mount point>/users/<username>

Parameters

- **username** –

- **mount_point** –

Returns

Return type

rekey (*key, nonce=None*)

Call to deprecated function ‘rekey’. This method will be removed in version ‘0.9.0’ Please use the ‘rekey’ method on

Docstring content from this method’s replacement copied below: Enter a single recovery key share to progress the rekey of the Vault.

If the threshold number of recovery key shares is reached, Vault will complete the rekey. Otherwise, this API must be called multiple times until that threshold is met. The rekey nonce operation must be provided with each call.

Supported methods: PUT: /sys/rekey/update. Produces: 200 application/json PUT: /sys/rekey-recovery-key/update. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single recovery share key.

- **nonce** (*str | unicode*) – Specifies the nonce of the rekey operation.

- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type dict

rekey_multi (*keys, nonce=None*)

Call to deprecated function ‘rekey_multi’. This method will be removed in version ‘0.9.0’ Please use the ‘rekey_multi’

Docstring content from this method’s replacement copied below: Enter multiple recovery key shares to progress the rekey of the Vault.

If the threshold number of recovery key shares is reached, Vault will complete the rekey.

Parameters

- **keys** (*list*) – Specifies multiple recovery share keys.
- **nonce** (*str | unicode*) – Specifies the nonce of the rekey operation.
- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The last response of the rekey request.

Return type response.Request

rekey_status

remount_secret_backend (*from_mount_point, to_mount_point*)

Call to deprecated function ‘remount_secret_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘remount_secret_backend’

Docstring content from this method’s replacement copied below: Move an already-mounted backend to a new mount point.

Supported methods: POST: /sys/remount. Produces: 204 (empty body)

Parameters

- **from_path** (*str | unicode*) – Specifies the previous mount point.
- **to_path** (*str | unicode*) – Specifies the new destination mount point.

Returns The response of the request.

Return type requests.Response

renew_secret (*lease_id, increment=None*)

Call to deprecated function ‘renew_secret’. This method will be removed in version ‘0.9.0’ Please use the ‘renew_secret’

Docstring content from this method’s replacement copied below: Renew a lease, requesting to extend the lease.

Supported methods: PUT: /sys/leases/renew. Produces: 200 application/json

Parameters

- **lease_id** (*str | unicode*) – The ID of the lease to extend.
- **increment** (*int*) – The requested amount of time (in seconds) to extend the lease.

Returns The JSON response of the request

Return type dict

renew_token (*token=None, increment=None, wrap_ttl=None*)

POST /auth/token/renew

POST /auth/token/renew-self

Parameters

- **token** –
- **increment** –
- **wrap_ttl** –

Returns

Return type

revoke_secret (*lease_id*)

Call to deprecated function ‘revoke_secret’. This method will be removed in version ‘0.9.0’ Please use the ‘revoke_le

Docstring content from this method’s replacement copied below: Revoke a lease immediately.

Supported methods: PUT: /sys/leases/revoke. Produces: 204 (empty body)

Parameters **lease_id** (*str | unicode*) – Specifies the ID of the lease to revoke.

Returns The response of the request.

Return type requests.Response

revoke_secret_prefix (*path_prefix*)

Call to deprecated function ‘revoke_secret_prefix’. This method will be removed in version ‘0.9.0’ Please use the ‘rev

Docstring content from this method’s replacement copied below: Revoke a lease immediately.

Supported methods: PUT: /sys/leases/revoke. Produces: 204 (empty body)

Parameters **lease_id** (*str | unicode*) – Specifies the ID of the lease to revoke.

Returns The response of the request.

Return type requests.Response

revoke_self_token ()

PUT /auth/token/revoke-self

Returns

Return type

revoke_token (*token, orphan=False, accessor=False*)

POST /auth/token/revoke

POST /auth/token/revoke-orphan

POST /auth/token/revoke-accessor

Parameters

- **token** –
- **orphan** –
- **accessor** –

Returns

Return type**revoke_token_prefix** (*prefix*)

POST /auth/token/revoke-prefix/<prefix>

Parameters **prefix** –**Returns****Return type****rotate** ()**Call to deprecated function ‘rotate’. This method will be removed in version ‘0.9.0’ Please use the ‘rotate_encryption**

Docstring content from this method’s replacement copied below: Trigger a rotation of the backend encryption key.

This is the key that is used to encrypt data written to the storage backend, and is not provided to operators. This operation is done online. Future values are encrypted with the new key, while old values are decrypted with previous encryption keys.

This path requires sudo capability in addition to update.

Supported methods: PUT: /sys/rotate. Produces: 204 (empty body)**Returns** The response of the request.**Return type** requests.Response**seal** ()**Call to deprecated function ‘seal’. This method will be removed in version ‘0.9.0’ Please use the ‘seal’ method on the**

Docstring content from this method’s replacement copied below: Seal the Vault.

In HA mode, only an active node can be sealed. Standby nodes should be restarted to get the same effect. Requires a token with root policy or sudo capability on the path.

Supported methods: PUT: /sys/seal. Produces: 204 (empty body)**Returns** The response of the request.**Return type** requests.Response**seal_status**

Read the seal status of the Vault.

This is an unauthenticated endpoint.

Supported methods: GET: /sys/seal-status. Produces: 200 application/json**Returns** The JSON response of the request.**Return type** dict**secrets**

Accessor for the Client instance’s secrets engines. Provided via the *hvac.api.SecretsEngines* class.

Returns This Client instance’s associated SecretsEngines instance.**Return type** *hvac.api.SecretsEngines***session**

set_policy (*name, rules*)

Call to deprecated function ‘set_policy’. This method will be removed in version ‘0.9.0’ Please use the ‘create_or_update_policy’.

Docstring content from this method’s replacement copied below: Add a new or update an existing policy.

Once a policy is updated, it takes effect immediately to all associated users.

Supported methods: PUT: /sys/policy/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the policy to create.
- **policy** (*str | unicode | dict*) – Specifies the policy document.
- **pretty_print** (*bool*) – If True, and provided a dict for the policy argument, send the policy JSON to Vault with “pretty” formatting.

Returns The response of the request.

Return type requests.Response

set_role_id (*role_name, role_id, mount_point='approve'*)

POST /auth/<mount_point>/role/<role name>/role-id

Parameters

- **role_name** –
- **role_id** –
- **mount_point** –

Returns

Return type

start_generate_root (*key, otp=False*)

Call to deprecated function ‘start_generate_root’. This method will be removed in version ‘0.9.0’ Please use the ‘start_generate_root’.

Docstring content from this method’s replacement copied below: Initialize a new root generation attempt.

Only a single root generation attempt can take place at a time. One (and only one) of otp or pgp_key are required.

Supported methods: PUT: /sys/generate-root/attempt. Produces: 200 application/json

Parameters

- **otp** (*str | unicode*) – Specifies a base64-encoded 16-byte value. The raw bytes of the token will be XOR’d with this value before being returned to the final unseal key provider.
- **pgp_key** (*str | unicode*) – Specifies a base64-encoded PGP public key. The raw bytes of the token will be encrypted with this value before being returned to the final unseal key provider.

Returns The JSON response of the request.

Return type dict

start_rekey (*secret_shares=5, secret_threshold=3, pgp_keys=None, backup=False*)

Call to deprecated function ‘start_rekey’. This method will be removed in version ‘0.9.0’ Please use the ‘start_rekey’

Docstring content from this method’s replacement copied below: Initializes a new rekey attempt.

Only a single recovery key rekeyattempt can take place at a time, and changing the parameters of a rekey requires canceling and starting a new rekey, which will also provide a new nonce.

Supported methods: PUT: /sys/rekey/init. Produces: 204 (empty body) PUT: /sys/rekey-recovery-key/init. Produces: 204 (empty body)

Parameters

- **secret_shares** (*int*) – Specifies the number of shares to split the master key into.
- **secret_threshold** (*int*) – Specifies the number of shares required to reconstruct the master key. This must be less than or equal to secret_shares.
- **pgp_keys** (*list*) – Specifies an array of PGP public keys used to encrypt the output unseal keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as secret_shares.
- **backup** (*bool*) – Specifies if using PGP-encrypted keys, whether Vault should also store a plaintext backup of the PGP-encrypted keys at core/unseal-keys-backup in the physical storage backend. These can then be retrieved and removed via the sys/rekey/backup endpoint.
- **require_verification** (*bool*) – This turns on verification functionality. When verification is turned on, after successful authorization with the current unseal keys, the new unseal keys are returned but the master key is not actually rotated. The new keys must be provided to authorize the actual rotation of the master key. This ensures that the new keys have been successfully saved and protects against a risk of the keys being lost after rotation but before they can be persisted. This can be used with without pgp_keys, and when used with it, it allows ensuring that the returned keys can be successfully decrypted before committing to the new shares, which the backup functionality does not provide.
- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON dict of the response.

Return type dict | request.Response

sys

Accessor for the Client instance’s system backend methods. Provided via the *hvac.api.SystemBackend* class.

Returns This Client instance’s associated SystemBackend instance.

Return type *hvac.api.SystemBackend*

token

token_role (*role*)

Returns the named token role.

Parameters *role* –

Returns

Return type

transit_create_key (*name*, *convergent_encryption=None*, *derived=None*, *exportable=None*, *key_type=None*, *mount_point='transit'*)

Call to deprecated function ‘transit_create_key’. This method will be removed in version ‘0.9.0’ Please use the ‘creat

Docstring content from this method’s replacement copied below: Create a new named encryption key of the specified type.

The values set here cannot be changed after key creation.

Supported methods: POST: `/{mount_point}/keys/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to create. This is specified as part of the URL.
- **convergent_encryption** (*bool*) – If enabled, the key will support convergent encryption, where the same plaintext creates the same ciphertext. This requires `derived` to be set to true. When enabled, each encryption(/decryption/unwrap/datakey) operation will derive a nonce value rather than randomly generate it.
- **derived** (*bool*) – Specifies if key derivation is to be used. If enabled, all encrypt/decrypt requests to this named key must provide a context which is used for key derivation.
- **exportable** (*bool*) – Enables keys to be exportable. This allows for all the valid keys in the key ring to be exported. Once set, this cannot be disabled.
- **allow_plaintext_backup** (*bool*) – If set, enables taking backup of named key in the plaintext format. Once set, this cannot be disabled.
- **key_type** (*str* | *unicode*) – Specifies the type of key to create. The currently-supported types are:
 - **aes256-gcm96**: AES-256 wrapped with GCM using a 96-bit nonce size AEAD
 - **chacha20-poly1305**: ChaCha20-Poly1305 AEAD (symmetric, supports derivation and convergent encryption)
 - **ed25519**: ED25519 (asymmetric, supports derivation).
 - **ecdsa-p256**: ECDSA using the P-256 elliptic curve (asymmetric)
 - **rsa-2048**: RSA with bit size of 2048 (asymmetric)
 - **rsa-4096**: RSA with bit size of 4096 (asymmetric)
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

transit_decrypt_data (*name*, *ciphertext*, *context=None*, *nonce=None*, *batch_input=None*, *mount_point='transit'*)

Call to deprecated function ‘transit_decrypt_data’. This method will be removed in version ‘0.9.0’ Please use the ‘de

Docstring content from this method’s replacement copied below: Decrypt the provided ciphertext using the named key.

Supported methods: POST: `/{mount_point}/decrypt/{name}`. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to decrypt against. This is specified as part of the URL.
- **ciphertext** (*str* | *unicode*) – the ciphertext to decrypt.

- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.
- **nonce** (*str | unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters ‘ciphertext’, ‘context’ and ‘nonce’ are also set, they will be ignored. Format for the input goes like this: `[dict(context="b64_context", ciphertext="b64_plaintext"), ...]`
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_delete_key (*name, mount_point='transit'*)

Call to deprecated function ‘transit_delete_key’. This method will be removed in version ‘0.9.0’ Please use the ‘delete_key’

Docstring content from this method’s replacement copied below: Delete a named encryption key.

It will no longer be possible to decrypt any data encrypted with the named key. Because this is a potentially catastrophic operation, the `deletion_allowed` tunable must be set in the key’s `/config` endpoint.

Supported methods: DELETE: `/{mount_point}/keys/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to delete. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

transit_encrypt_data (*name, plaintext, context=None, key_version=None, nonce=None, batch_input=None, key_type=None, convergent_encryption=None, mount_point='transit'*)

Call to deprecated function ‘transit_encrypt_data’. This method will be removed in version ‘0.9.0’ Please use the ‘encrypt_data’

Docstring content from this method’s replacement copied below: Encrypt the provided plaintext using the named key.

This path supports the create and update policy capabilities as follows: if the user has the create capability for this endpoint in their policies, and the key does not exist, it will be upserted with default values (whether the key requires derivation depends on whether the context parameter is empty or not). If the user only has update capability and the key does not exist, an error will be returned.

Supported methods: POST: `/{mount_point}/encrypt/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to encrypt against. This is specified as part of the URL.
- **plaintext** (*str | unicode*) – Specifies base64 encoded plaintext to be encoded.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled for this key.

- **key_version** (*int*) – Specifies the version of the key to use for encryption. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **nonce** (*str | unicode*) – Specifies the base64 encoded nonce value. This must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+. The value must be exactly 96 bits (12 bytes) long and the user must ensure that for any given context (and thus, any given encryption key) this nonce value is never reused.
- **batch_input** (*List[dict]*) – Specifies a list of items to be encrypted in a single batch. When this parameter is set, if the parameters ‘plaintext’, ‘context’ and ‘nonce’ are also set, they will be ignored. The format for the input is: `[dict(context="b64_context", plaintext="b64_plaintext"), ...]`
- **type** (*str | unicode*) – This parameter is required when encryption key is expected to be created. When performing an upsert operation, the type of key to create.
- **convergent_encryption** (*str | unicode*) – This parameter will only be used when a key is expected to be created. Whether to support convergent encryption. This is only supported when using a key with key derivation enabled and will require all requests to carry both a context and 96-bit (12-byte) nonce. The given nonce will be used in place of a randomly generated nonce. As a result, when the same context and nonce are supplied, the same ciphertext is generated. It is very important when using this mode that you ensure that all nonces are unique for a given context. Failing to do so will severely impact the ciphertext’s security.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `requests.Response`

transit_export_key (*name, key_type, version=None, mount_point='transit'*)

Call to deprecated function ‘transit_export_key’. This method will be removed in version ‘0.9.0’ Please use the ‘export_key’ method.

Docstring content from this method’s replacement copied below: Return the named key.

The keys object shows the value of the key for each version. If version is specified, the specific version will be returned. If latest is provided as the version, the current key will be provided. Depending on the type of key, different information may be returned. The key must be exportable to support this operation and the version must still be valid.

Supported methods: GET: `/{mount_point}/export/{key_type}/{name}(/{version})`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to read information about. This is specified as part of the URL.
- **key_type** (*str | unicode*) – Specifies the type of the key to export. This is specified as part of the URL. Valid values are: encryption-key signing-key hmac-key
- **version** (*str | unicode*) – Specifies the version of the key to read. If omitted, all versions of the key will be returned. If the version is set to latest, the current key will be returned.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_generate_data_key (*name*, *key_type*, *context=None*, *nonce=None*, *bits=None*, *mount_point='transit'*)

Call to deprecated function ‘transit_generate_data_key’. This method will be removed in version ‘0.9.0’ Please use the ‘

Docstring content from this method’s replacement copied below: Generates a new high-entropy key and the value encrypted with the named key.

Optionally return the plaintext of the key as well. Whether plaintext is returned depends on the path; as a result, you can use Vault ACL policies to control whether a user is allowed to retrieve the plaintext value of a key. This is useful if you want an untrusted user or operation to generate keys that are then made available to trusted users.

Supported methods: POST: `/{mount_point}/datakey/{key_type}/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to use to encrypt the datakey. This is specified as part of the URL.
- **key_type** (*str | unicode*) – Specifies the type of key to generate. If plaintext, the plaintext key will be returned along with the ciphertext. If wrapped, only the ciphertext value will be returned. This is specified as part of the URL.
- **context** (*str | unicode*) – Specifies the key derivation context, provided as a base64-encoded string. This must be provided if derivation is enabled.
- **nonce** (*str | unicode*) – Specifies a nonce value, provided as base64 encoded. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+. The value must be exactly 96 bits (12 bytes) long and the user must ensure that for any given context (and thus, any given encryption key) this nonce value is never reused.
- **bits** (*int*) – Specifies the number of bits in the desired key. Can be 128, 256, or 512.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_generate_hmac (*name*, *hmac_input*, *key_version=None*, *algorithm=None*, *mount_point='transit'*)

Call to deprecated function ‘transit_generate_hmac’. This method will be removed in version ‘0.9.0’ Please use the ‘

Docstring content from this method’s replacement copied below: Return the digest of given data using the specified hash algorithm and the named key.

The key can be of any type supported by transit; the raw key will be marshaled into bytes to be used for the HMAC function. If the key is of a type that supports rotation, the latest (current) version will be used.

Supported methods: POST: `/{mount_point}/hmac/{name}/{algorithm}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to generate hmac against. This is specified as part of the URL.
- **hash_input** – Specifies the base64 encoded input data.

- **key_version** (*int*) – Specifies the version of the key to use for the operation. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **algorithm** (*str | unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_generate_rand_bytes (*data_bytes=None, output_format=None, mount_point='transit'*)

Call to deprecated function ‘transit_generate_rand_bytes’. This method will be removed in version ‘0.9.0’ Please use

Docstring content from this method’s replacement copied below: Return high-quality random bytes of the specified length.

Supported methods: POST: `/{{mount_point}}/random/{{bytes}}`. Produces: 200 application/json

Parameters

- **n_bytes** (*int*) – Specifies the number of bytes to return. This value can be specified either in the request body, or as a part of the URL.
- **output_format** (*str | unicode*) – Specifies the output encoding. Valid options are hex or base64.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_hash_data (*hash_input, algorithm=None, output_format=None, mount_point='transit'*)

Call to deprecated function ‘transit_hash_data’. This method will be removed in version ‘0.9.0’ Please use the ‘hash_

Docstring content from this method’s replacement copied below: Return the cryptographic hash of given data using the specified algorithm.

Supported methods: POST: `/{{mount_point}}/hash/{{algorithm}}`. Produces: 200 application/json

Parameters

- **hash_input** (*str | unicode*) – Specifies the base64 encoded input data.
- **algorithm** (*str | unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **output_format** (*str | unicode*) – Specifies the output encoding. This can be either hex or base64.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_list_keys (*mount_point='transit'*)

Call to deprecated function ‘transit_list_keys’. This method will be removed in version ‘0.9.0’ Please use the ‘list_keys’.
 Docstring content from this method’s replacement copied below: List keys.

Only the key names are returned (not the actual keys themselves).

Supported methods: LIST: `/{{mount_point}}/keys`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

`transit_read_key` (*name, mount_point='transit'*)

Call to deprecated function ‘transit_read_key’. This method will be removed in version ‘0.9.0’ Please use the ‘read_key’.
 Docstring content from this method’s replacement copied below: Read information about a named encryption key.

The keys object shows the creation time of each key version; the values are not the keys themselves. Depending on the type of key, different information may be returned, e.g. an asymmetric key will return its public key in a standard format for the type.

Supported methods: GET: `/{{mount_point}}/keys/{{name}}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to read. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_key request.

Return type requests.Response

`transit_rewrap_data` (*name, ciphertext, context=None, key_version=None, nonce=None, batch_input=None, mount_point='transit'*)

Call to deprecated function ‘transit_rewrap_data’. This method will be removed in version ‘0.9.0’ Please use the ‘rewrap’.
 Docstring content from this method’s replacement copied below: Rewrap the provided ciphertext using the latest version of the named key.

Because this never returns plaintext, it is possible to delegate this functionality to untrusted users or scripts.

Supported methods: POST: `/{{mount_point}}/rewrap/{{name}}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to re-encrypt against. This is specified as part of the URL.
- **ciphertext** (*str | unicode*) – Specifies the ciphertext to re-encrypt.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.
- **key_version** (*int*) – Specifies the version of the key to use for the operation. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.

- **nonce** (*str | unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters ‘ciphertext’, ‘context’ and ‘nonce’ are also set, they will be ignored. Format for the input goes like this: [dict(context=“b64_context”, ciphertext=“b64_plaintext”), ...]
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_rotate_key (*name, mount_point='transit'*)

Call to deprecated function ‘transit_rotate_key’. This method will be removed in version ‘0.9.0’ Please use the ‘rotate_key’.

Docstring content from this method’s replacement copied below: Rotate the version of the named key.

After rotation, new plaintext requests will be encrypted with the new version of the key. To upgrade ciphertext to be encrypted with the latest version of the key, use the rewrap endpoint. This is only supported with keys that support encryption and decryption operations.

Supported methods: POST: /{mount_point}/keys/{name}/rotate. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to read information about. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

transit_sign_data (*name, input_data, key_version=None, algorithm=None, context=None, pre_hashed=None, mount_point='transit', signature_algorithm='pss'*)

Call to deprecated function ‘transit_sign_data’. This method will be removed in version ‘0.9.0’ Please use the ‘sign_data’.

Docstring content from this method’s replacement copied below: Return the cryptographic signature of the given data using the named key and the specified hash algorithm.

The key must be of a type that supports signing.

Supported methods: POST: /{mount_point}/sign/{name}({hash_algorithm}). Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to use for signing. This is specified as part of the URL.
- **hash_input** (*str | unicode*) – Specifies the base64 encoded input data.
- **key_version** (*int*) – Specifies the version of the key to use for signing. If not set, uses the latest version. Must be greater than or equal to the key’s min_encryption_version, if set.

- **hash_algorithm** (*str | unicode*) – Specifies the hash algorithm to use for supporting key types (notably, not including ed25519 which specifies its own hash algorithm). This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **context** (*str | unicode*) – Base64 encoded context for key derivation. Required if key derivation is enabled; currently only available with ed25519 keys.
- **prehashed** (*bool*) – Set to true when the input is already hashed. If the key type is rsa-2048 or rsa-4096, then the algorithm used to hash the input should be indicated by the hash_algorithm parameter. Just as the value to sign should be the base64-encoded representation of the exact binary data you want signed, when set, input is expected to be base64-encoded binary hashed data, not hex-formatted. (As an example, on the command line, you could generate a suitable input via openssl dgst -sha256 -binary | base64.)
- **signature_algorithm** (*str | unicode*) – When using a RSA key, specifies the RSA signature algorithm to use for signing. Supported signature types are: pss, pkcs1v15
- **marshaling_algorithm** (*str | unicode*) – Specifies the way in which the signature should be marshaled. This currently only applies to ECDSA keys. Supported types are: asn1, jws
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

transit_update_key (*name, min_decryption_version=None, min_encryption_version=None, deletion_allowed=None, mount_point='transit'*)

Call to deprecated function ‘transit_update_key’. This method will be removed in version ‘0.9.0’ Please use the ‘update_key’ method.

Docstring content from this method’s replacement copied below: Tune configuration values for a given key.

These values are returned during a read operation on the named key.

Supported methods: POST: /{mount_point}/keys/{name}/config. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to update configuration for.
- **min_decryption_version** (*int*) – Specifies the minimum version of ciphertext allowed to be decrypted. Adjusting this as part of a key rotation policy can prevent old copies of ciphertext from being decrypted, should they fall into the wrong hands. For signatures, this value controls the minimum version of signature that can be verified against. For HMACs, this controls the minimum version of a key allowed to be used as the key for verification.
- **min_encryption_version** (*int*) – Specifies the minimum version of the key that can be used to encrypt plaintext, sign payloads, or generate HMACs. Must be 0 (which will use the latest version) or a value greater or equal to min_decryption_version.
- **deletion_allowed** (*bool*) – Specifies if the key is allowed to be deleted.
- **exportable** (*bool*) – Enables keys to be exportable. This allows for all the valid keys in the key ring to be exported. Once set, this cannot be disabled.
- **allow_plaintext_backup** (*bool*) – If set, enables taking backup of named key in the plaintext format. Once set, this cannot be disabled.

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

```
transit_verify_signed_data (name, input_data, algorithm=None, signature=None,
                             hmac=None, context=None, prehashed=None,
                             mount_point='transit', signature_algorithm='pss')
```

Call to deprecated function ‘transit_verify_signed_data’. This method will be removed in version ‘0.9.0’ Please use the

Docstring content from this method’s replacement copied below: Return whether the provided signature is valid for the given data.

Supported methods: POST: /{mount_point}/verify/{name}/{hash_algorithm}). Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key that was used to generate the signature or HMAC.
- **hash_input** – Specifies the base64 encoded input data.
- **signature** (*str | unicode*) – Specifies the signature output from the /transit/sign function. Either this must be supplied or hmac must be supplied.
- **hmac** (*str | unicode*) – Specifies the signature output from the /transit/hmac function. Either this must be supplied or signature must be supplied.
- **hash_algorithm** (*str | unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **context** (*str | unicode*) – Base64 encoded context for key derivation. Required if key derivation is enabled; currently only available with ed25519 keys.
- **prehashed** (*bool*) – Set to true when the input is already hashed. If the key type is rsa-2048 or rsa-4096, then the algorithm used to hash the input should be indicated by the hash_algorithm parameter.
- **signature_algorithm** (*str | unicode*) – When using a RSA key, specifies the RSA signature algorithm to use for signature verification. Supported signature types are: pss, pkcs1v15
- **marshaling_algorithm** (*str | unicode*) – Specifies the way in which the signature should be marshaled. This currently only applies to ECDSA keys. Supported types are: asn1, jws
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

```
tune_auth_backend (backend_type, mount_point=None, default_lease_ttl=None,
                   max_lease_ttl=None, description=None, audit_non_hmac_request_keys=None,
                   audit_non_hmac_response_keys=None, listing_visibility="", passthrough_request_headers=None)
```

Call to deprecated function ‘tune_auth_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘tune

Docstring content from this method’s replacement copied below: Tune configuration parameters for a given auth path.

This endpoint requires sudo capability on the final path, but the same functionality can be achieved without sudo via `sys/mounts/auth/{auth-path}/tune`.

Supported methods: POST: `/sys/auth/{path}/tune`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.
- **default_lease_ttl** (*int*) – Specifies the default time-to-live. If set on a specific auth path, this overrides the global default.
- **max_lease_ttl** (*int*) – The maximum time-to-live. If set on a specific auth path, this overrides the global default.
- **description** (*str | unicode*) – Specifies the description of the mount. This overrides the current stored value, if any.
- **audit_non_hmac_request_keys** (*array*) – Specifies the list of keys that will not be HMAC’d by audit devices in the request data object.
- **audit_non_hmac_response_keys** (*list*) – Specifies the list of keys that will not be HMAC’d by audit devices in the response data object.
- **listing_visibility** (*list*) – Specifies whether to show this mount in the UI-specific listing endpoint. Valid values are “unauth” or “”.
- **passthrough_request_headers** (*list*) – List of headers to whitelist and pass from the request to the backend.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

```
tune_secret_backend (backend_type, mount_point=None, default_lease_ttl=None,
                    max_lease_ttl=None, description=None, audit_non_hmac_request_keys=None,
                    audit_non_hmac_response_keys=None, listing_visibility=None,
                    passthrough_request_headers=None)
```

Call to deprecated function ‘tune_secret_backend’. This method will be removed in version ‘0.9.0’ Please use the ‘tu

Docstring content from this method’s replacement copied below: Tune configuration parameters for a given mount point.

Supported methods: POST: `/sys/mounts/{path}/tune`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.
- **mount_point** (*str*) – The path the associated secret backend is mounted
- **description** (*str*) – Specifies the description of the mount. This overrides the current stored value, if any.
- **default_lease_ttl** (*int*) – Default time-to-live. This overrides the global default. A value of 0 is equivalent to the system default TTL
- **max_lease_ttl** (*int*) – Maximum time-to-live. This overrides the global default. A value of 0 are equivalent and set to the system max TTL.

- **audit_non_hmac_request_keys** (*list*) – Specifies the comma-separated list of keys that will not be HMAC'd by audit devices in the request data object.
- **audit_non_hmac_response_keys** (*list*) – Specifies the comma-separated list of keys that will not be HMAC'd by audit devices in the response data object.
- **listing_visibility** (*str*) – Specifies whether to show this mount in the UI-specific listing endpoint. Valid values are “unauth” or “”.
- **passthrough_request_headers** (*str*) – Comma-separated list of headers to whitelist and pass from the request to the backend.
- **options** (*dict*) – Specifies mount type specific options that are passed to the backend.
 - **version**: <KV> The version of the KV to mount. Set to “2” for mount KV v2.
- **force_no_cache** (*bool*) – Disable caching.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response from the request.

Return type request.Response

unseal (*key*)

Call to deprecated function ‘unseal’. This method will be removed in version ‘0.9.0’ Please use the ‘submit_unseal_k

Docstring content from this method’s replacement copied below: Enter a single master key share to progress the unsealing of the Vault.

If the threshold number of master key shares is reached, Vault will attempt to unseal the Vault. Otherwise, this API must be called multiple times until that threshold is met.

Either the key or reset parameter must be provided; if both are provided, reset takes precedence.

Supported methods: PUT: /sys/unseal. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single master key share. This is required unless reset is true.
- **reset** (*bool*) – Specifies if previously-provided unseal keys are discarded and the unseal process is reset.
- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the request.

Return type dict

unseal_multi (*keys*)

Call to deprecated function ‘unseal_multi’. This method will be removed in version ‘0.9.0’ Please use the ‘submit_un

Docstring content from this method’s replacement copied below: Enter multiple master key share to progress the unsealing of the Vault.

Parameters

- **keys** (*List[str]*) – List of master key shares.

- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the last unseal request.

Return type dict

`unseal_reset ()`

Call to deprecated function ‘unseal_reset’. This method will be removed in version ‘0.9.0’ Please use the ‘submit_unseal’ method.

Docstring content from this method’s replacement copied below: Enter a single master key share to progress the unsealing of the Vault.

If the threshold number of master key shares is reached, Vault will attempt to unseal the Vault. Otherwise, this API must be called multiple times until that threshold is met.

Either the key or reset parameter must be provided; if both are provided, reset takes precedence.

Supported methods: PUT: /sys/unseal. Produces: 200 application/json

Parameters

- **key** (*str* | *unicode*) – Specifies a single master key share. This is required unless reset is true.
- **reset** (*bool*) – Specifies if previously-provided unseal keys are discarded and the unseal process is reset.
- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the request.

Return type dict

`unwrap (token=None)`

Call to deprecated function ‘unwrap’. This method will be removed in version ‘0.9.0’ Please use the ‘unwrap’ method.

Docstring content from this method’s replacement copied below: Return the original response inside the given wrapping token.

Unlike simply reading cubbyhole/response (which is deprecated), this endpoint provides additional validation checks on the token, returns the original value on the wire rather than a JSON string representation of it, and ensures that the response is properly audit-logged.

Supported methods: POST: /sys/wrapping/unwrap. Produces: 200 application/json

Parameters **token** (*str* | *unicode*) – Specifies the wrapping token ID. This is required if the client token is not the wrapping token. Do not use the wrapping token in both locations.

Returns The JSON response of the request.

Return type dict

`update_userpass_password (username, password, mount_point='userpass')`

POST /auth/<mount point>/users/<username>/password

Parameters

- **username** –

- `password` –
- `mount_point` –

Returns

Return type

update_userpass_policies (*username, policies, mount_point='userpass'*)
 POST /auth/<mount point>/users/<username>/policies

Parameters

- `username` –
- `policies` –
- `mount_point` –

Returns

Return type

`url`

static urljoin (**args*)

Call to deprecated function ‘urljoin’. This method will be removed in version ‘0.8.0’ Please use the ‘urljoin’ method
 Docstring content from this method’s replacement copied below: Joins given arguments into a url.
 Trailing and leading slashes are stripped for each argument.

Parameters *args* (*str | unicode*) – Multiple parts of a URL to be combined into one string.

Returns Full URL combining all provided arguments

Return type `str | unicode`

write (*path, wrap_ttl=None, **kwargs*)
 POST /<path>

Parameters

- `path` –
- `wrap_ttl` –
- `kwargs` –

Returns

Return type

4.2 hvac.api

Collection of Vault API endpoint classes.

class `hvac.api.AuthMethods` (*adapter*)

Bases: `hvac.api.vault_api_category.VaultApiCategory`

Auth Methods.

`implemented_classes` = [`<class 'hvac.api.auth_methods.azure.Azure'>`, `<class 'hvac.api.a`

`unimplemented_classes` = [`'AppId'`, `'AppRole'`, `'AliCloud'`, `'Jwt'`, `'Cert'`, `'Token'`]

```

class hvac.api.SecretsEngines(adapter)
    Bases: hvac.api.vault_api_category.VaultApiCategory

    Secrets Engines.

    implemented_classes = [<class 'hvac.api.secrets_engines.aws.Aws'>, <class 'hvac.api.secrets_engines.azure.Azure'>, <class 'hvac.api.secrets_engines.gcpkms.GcpKms'>, <class 'hvac.api.secrets_engines.nomad.Nomad'>, <class 'hvac.api.secrets_engines.ssh.Ssh'>, <class 'hvac.api.secrets_engines.totp.Totp'>, <class 'hvac.api.secrets_engines.cassandra.Cassandra'>]
    unimplemented_classes = ['AliCloud', 'Azure', 'GcpKms', 'Nomad', 'Ssh', 'TOTP', 'Cassandra']

class hvac.api.SystemBackend(adapter)
    Bases: hvac.api.vault_api_category.VaultApiCategory, hvac.api.system_backend.audit.Audit, hvac.api.system_backend.auth.Auth, hvac.api.system_backend.capabilities.Capabilities, hvac.api.system_backend.health.Health, hvac.api.system_backend.init.Init, hvac.api.system_backend.key.Key, hvac.api.system_backend.leader.Leader, hvac.api.system_backend.lease.Lease, hvac.api.system_backend.mount.Mount, hvac.api.system_backend.namespace.Namespace, hvac.api.system_backend.policy.Policy, hvac.api.system_backend.seal.Seal, hvac.api.system_backend.wrapping.Wrapping

    __init__(adapter)
        API Category class constructor.

        Parameters adapter (hvac.adapters.Adapter) – Instance of hvac.adapters.Adapter; used for performing HTTP requests.

    implemented_classes = [<class 'hvac.api.system_backend.audit.Audit'>, <class 'hvac.api.system_backend.auth.Auth'>, <class 'hvac.api.system_backend.capabilities.Capabilities'>, <class 'hvac.api.system_backend.health.Health'>, <class 'hvac.api.system_backend.init.Init'>, <class 'hvac.api.system_backend.key.Key'>, <class 'hvac.api.system_backend.leader.Leader'>, <class 'hvac.api.system_backend.lease.Lease'>, <class 'hvac.api.system_backend.mount.Mount'>, <class 'hvac.api.system_backend.namespace.Namespace'>, <class 'hvac.api.system_backend.policy.Policy'>, <class 'hvac.api.system_backend.seal.Seal'>, <class 'hvac.api.system_backend.wrapping.Wrapping'>]
    unimplemented_classes = []

class hvac.api.VaultApiBase(adapter)
    Bases: object

    Base class for API endpoints.

    __init__(adapter)
        Default api class constructor.

        Parameters adapter (hvac.adapters.Adapter) – Instance of hvac.adapters.Adapter; used for performing HTTP requests.

class hvac.api.VaultApiCategory(adapter)
    Bases: hvac.api.vault_api_base.VaultApiBase

    Base class for API categories.

    __init__(adapter)
        API Category class constructor.

        Parameters adapter (hvac.adapters.Adapter) – Instance of hvac.adapters.Adapter; used for performing HTTP requests.

adapter
    Retrieve the adapter instance under the “_adapter” property in use by this class.

    Returns The adapter instance in use by this class.

    Return type hvac.adapters.Adapter

static get_private_attr_name(class_name)
    Helper method to prepend a leading underscore to a provided class name.

    Parameters class_name (str/unicode) – Name of a class under this category.

    Returns The private attribute label for the provided class.

```

Return type str

implemented_classes

List of implemented classes under this category.

Returns List of implemented classes under this category.

Return type List[hvac.api.VaultApiBase]

unimplemented_classes

List of known unimplemented classes under this category.

Returns List of known unimplemented classes under this category.

Return type List[str]

4.3 hvac.api.auth_methods

Collection of classes for various Vault auth methods.

class hvac.api.auth_methods.**AuthMethods** (*adapter*)

Bases: hvac.api.vault_api_category.VaultApiCategory

Auth Methods.

implemented_classes = [<class 'hvac.api.auth_methods.azure.Azure'>, <class 'hvac.api.a

unimplemented_classes = ['AppId', 'AppRole', 'AliCloud', 'Jwt', 'Cert', 'Token']

class hvac.api.auth_methods.**Azure** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

Azure Auth Method (API).

Reference: <https://www.vaultproject.io/api/auth/azure/index.html>

configure (*tenant_id*, *resource*, *environment=None*, *client_id=None*, *client_secret=None*, *mount_point='azure'*)

Configure the credentials required for the plugin to perform API calls to Azure.

These credentials will be used to query the metadata about the virtual machine.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **tenant_id** (*str* | *unicode*) – The tenant id for the Azure Active Directory organization.
- **resource** (*str* | *unicode*) – The configured URL for the application registered in Azure Active Directory.
- **environment** (*str* | *unicode*) – The Azure cloud environment. Valid values: AzurePublicCloud, AzureUSGovernmentCloud, AzureChinaCloud, AzureGermanCloud.
- **client_id** (*str* | *unicode*) – The client id for credentials to query the Azure APIs. Currently read permissions to query compute resources are required.
- **client_secret** (*str* | *unicode*) – The client secret for credentials to query the Azure APIs.
- **mount_point** (*str* | *unicode*) – The “path” the azure auth method was mounted on.

Returns The response of the request.

Return type requests.Response

create_role (*name*, *policies=None*, *ttl=None*, *max_ttl=None*, *period=None*,
bound_service_principal_ids=None, *bound_group_ids=None*, *bound_locations=None*,
bound_subscription_ids=None, *bound_resource_groups=None*,
bound_scale_sets=None, *num_uses=None*, *mount_point='azure'*)

Create a role in the method.

Role types have specific entities that can perform login operations against this endpoint. Constraints specific to the role type must be set on the role. These are applied to the authenticated entities attempting to login.

Supported methods: POST: /auth/{mount_point}/role/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **policies** (*str | list*) – Policies to be set on tokens issued using this role.
- **num_uses** (*int*) – Number of uses to set on a token produced by this role.
- **ttl** (*str | unicode*) – The TTL period of tokens issued using this role in seconds.
- **max_ttl** (*str | unicode*) – The maximum allowed lifetime of tokens issued in seconds using this role.
- **period** (*str | unicode*) – If set, indicates that the token generated using this role should never expire. The token should be renewed within the duration specified by this value. At each renewal, the token’s TTL will be set to the value of this parameter.
- **bound_service_principal_ids** (*list*) – The list of Service Principal IDs that login is restricted to.
- **bound_group_ids** (*list*) – The list of group ids that login is restricted to.
- **bound_locations** (*list*) – The list of locations that login is restricted to.
- **bound_subscription_ids** (*list*) – The list of subscription IDs that login is restricted to.
- **bound_resource_groups** (*list*) – The list of resource groups that login is restricted to.
- **bound_scale_sets** (*list*) – The list of scale set names that the login is restricted to.
- **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The response of the request.

Return type requests.Response

delete_config (*mount_point='azure'*)

Delete the previously configured Azure config and credentials.

Supported methods: DELETE: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The response of the request.

Return type requests.Response

delete_role (*name*, *mount_point='azure'*)

Delete the previously registered role.

Supported methods: DELETE: /auth/{mount_point}/role/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The response of the request.

Return type requests.Response

list_roles (*mount_point='azure'*)

List all the roles that are registered with the plugin.

Supported methods: LIST: /auth/{mount_point}/role. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The “data” key from the JSON response of the request.

Return type dict

login (*role*, *jwt*, *subscription_id=None*, *resource_group_name=None*, *vm_name=None*, *vmss_name=None*, *use_token=True*, *mount_point='azure'*)

Fetch a token.

This endpoint takes a signed JSON Web Token (JWT) and a role name for some entity. It verifies the JWT signature to authenticate that entity and then authorizes the entity for the given role.

Supported methods: POST: /auth/{mount_point}/login. Produces: 200 application/json

Parameters

- **role** (*str | unicode*) – Name of the role against which the login is being attempted.
- **jwt** (*str | unicode*) – Signed JSON Web Token (JWT) from Azure MSI.
- **subscription_id** (*str | unicode*) – The subscription ID for the machine that generated the MSI token. This information can be obtained through instance metadata.
- **resource_group_name** (*str | unicode*) – The resource group for the machine that generated the MSI token. This information can be obtained through instance metadata.
- **vm_name** (*str | unicode*) – The virtual machine name for the machine that generated the MSI token. This information can be obtained through instance metadata. If *vmss_name* is provided, this value is ignored.
- **vmss_name** (*str | unicode*) – The virtual machine scale set name for the machine that generated the MSI token. This information can be obtained through instance metadata.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the *hvac.adapters.Adapter()* instance under the *_adapater* Client attribute.

- **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The JSON response of the request.

Return type dict

read_config (*mount_point='azure'*)

Return the previously configured config, including credentials.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The data key from the JSON response of the request.

Return type dict

read_role (*name, mount_point='azure'*)

Read the previously registered role configuration.

Supported methods: GET: /auth/{mount_point}/role/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The “data” key from the JSON response of the request.

Return type dict

class hvac.api.auth_methods.Gcp (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

Google Cloud Auth Method (API).

Reference: https://www.vaultproject.io/api/auth/{mount_point}/index.html

configure (*credentials=None, google_certs_endpoint='https://www.googleapis.com/oauth2/v3/certs', mount_point='gcp'*)

Configure the credentials required for the GCP auth method to perform API calls to Google Cloud.

These credentials will be used to query the status of IAM entities and get service account or other Google public certificates to confirm signed JWTs passed in during login.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **credentials** (*str | unicode*) – A JSON string containing the contents of a GCP credentials file. The credentials file must have the following permissions: *iam.serviceAccounts.get*, *iam.serviceAccountKeys.get*. If this value is empty, Vault will try to use Application Default Credentials from the machine on which the Vault server is running. The project must have the iam.googleapis.com API enabled.
- **google_certs_endpoint** (*str | unicode*) – The Google OAuth2 endpoint from which to obtain public certificates. This is used for testing and should generally not be set by end users.

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

create_role (*name, role_type, project_id, ttl=None, max_ttl=None, period=None, policies=None, bound_service_accounts=None, max_jwt_exp=None, allow_gce_inference=None, bound_zones=None, bound_regions=None, bound_instance_groups=None, bound_labels=None, mount_point='gcp'*)

Register a role in the GCP auth method.

Role types have specific entities that can perform login operations against this endpoint. Constraints specific to the role type must be set on the role. These are applied to the authenticated entities attempting to login.

Supported methods: POST: /auth/{mount_point}/role/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name of the role.
- **role_type** (*str | unicode*) – The type of this role. Certain fields correspond to specific roles and will be rejected otherwise.
- **project_id** (*str | unicode*) – The GCP project ID. Only entities belonging to this project can authenticate with this role.
- **ttl** (*str | unicode*) – The TTL period of tokens issued using this role. This can be specified as an integer number of seconds or as a duration value like “5m”.
- **max_ttl** (*str | unicode*) – The maximum allowed lifetime of tokens issued in seconds using this role. This can be specified as an integer number of seconds or as a duration value like “5m”.
- **period** (*str | unicode*) – If set, indicates that the token generated using this role should never expire. The token should be renewed within the duration specified by this value. At each renewal, the token’s TTL will be set to the value of this parameter. This can be specified as an integer number of seconds or as a duration value like “5m”.
- **policies** (*list*) – The list of policies to be set on tokens issued using this role.
- **bound_service_accounts** (*list*) – <required for iam> A list of service account emails or IDs that login is restricted to. If set to *, all service accounts are allowed (role will still be bound by project). Will be inferred from service account used to issue metadata token for GCE instances.
- **max_jwt_exp** (*str | unicode*) – <iam only> The number of seconds past the time of authentication that the login param JWT must expire within. For example, if a user attempts to login with a token that expires within an hour and this is set to 15 minutes, Vault will return an error prompting the user to create a new signed JWT with a shorter exp. The GCE metadata tokens currently do not allow the exp claim to be customized.
- **allow_gce_inference** (*bool*) – <iam only> A flag to determine if this role should allow GCE instances to authenticate by inferring service accounts from the GCE identity metadata token.
- **bound_zones** (*list*) – <gce only> The list of zones that a GCE instance must belong to in order to be authenticated. If bound_instance_groups is provided, it is assumed to be a zonal group and the group must belong to this zone.

- **bound_regions** (*list*) – <gce only> The list of regions that a GCE instance must belong to in order to be authenticated. If `bound_instance_groups` is provided, it is assumed to be a regional group and the group must belong to this region. If `bound_zones` are provided, this attribute is ignored.
- **bound_instance_groups** (*list*) – <gce only> The instance groups that an authorized instance must belong to in order to be authenticated. If specified, either `bound_zones` or `bound_regions` must be set too.
- **bound_labels** (*list*) – <gce only> A list of GCP labels formatted as “key:value” strings that must be set on authorized GCE instances. Because GCP labels are not currently ACL’d, we recommend that this be used in conjunction with other restrictions.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the request.

Return type requests.Response

delete_config (*mount_point='gcp'*)

Delete all GCP configuration data. This operation is idempotent.

Supported methods: DELETE: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_role (*role, mount_point='gcp'*)

Delete the previously registered role.

Supported methods: DELETE: /auth/{mount_point}/role/{role}. Produces: 204 (empty body)

Parameters

- **role** (*str | unicode*) – The name of the role to delete.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

edit_labels_on_gce_role (*name, add=None, remove=None, mount_point='gcp'*)

Edit labels for an existing GCE role in the backend.

This allows you to add or remove labels (keys, values, or both) from the list of keys on the role.

Supported methods: POST: /auth/{mount_point}/role/{name}/labels. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name of an existing gce role. This will return an error if role is not a gce type role.
- **add** (*list*) – The list of key:value labels to add to the GCE role’s bound labels.
- **remove** (*list*) – The list of label keys to remove from the role’s bound labels. If any of the specified keys do not exist, no error is returned (idempotent).

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the `edit_labels_on_gce_role` request.

Return type `requests.Response`

edit_service_accounts_on_iam_role (*name*, *add=None*, *remove=None*,
mount_point='gcp')

Edit service accounts for an existing IAM role in the GCP auth method.

This allows you to add or remove service accounts from the list of service accounts on the role.

Supported methods: POST: `/auth/{mount_point}/role/{name}/service-accounts`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name of an existing iam type role. This will return an error if role is not an iam type role.
- **add** (*list*) – The list of service accounts to add to the role’s service accounts.
- **remove** (*list*) – The list of service accounts to remove from the role’s service accounts.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

list_roles (*mount_point='gcp'*)

List all the roles that are registered with the plugin.

Supported methods: LIST: `/auth/{mount_point}/roles`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the request.

Return type `dict`

login (*role, jwt, use_token=True, mount_point='gcp'*)

Login to retrieve a Vault token via the GCP auth method.

This endpoint takes a signed JSON Web Token (JWT) and a role name for some entity. It verifies the JWT signature with Google Cloud to authenticate that entity and then authorizes the entity for the given role.

Supported methods: POST: `/auth/{mount_point}/login`. Produces: 200 application/json

Parameters

- **role** (*str | unicode*) – The name of the role against which the login is being attempted.
- **jwt** (*str | unicode*) – A signed JSON web token
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_config (*mount_point='gcp'*)

Read the configuration, if any, including credentials.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the request.

Return type dict

read_role (*name, mount_point='gcp'*)

Read the previously registered role configuration.

Supported methods: GET: /auth/{mount_point}/role/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – The name of the role to read.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the read_role request.

Return type JSON

class hvac.api.auth_methods.**GitHub** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

GitHub Auth Method (API).

Reference: <https://www.vaultproject.io/api/auth/github/index.html>

configure (*organization, base_url=None, ttl=None, max_ttl=None, mount_point='github'*)

Configure the connection parameters for GitHub.

This path honors the distinction between the create and update capabilities inside ACL policies.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **organization** (*str | unicode*) – The organization users must be part of.
- **base_url** (*str | unicode*) – The API endpoint to use. Useful if you are running GitHub Enterprise or an API-compatible authentication server.
- **ttl** (*str | unicode*) – Duration after which authentication will be expired.
- **max_ttl** (*str | unicode*) – Maximum duration after which authentication will be expired.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the configure_method request.

Return type requests.Response

login (*token*, *use_token=True*, *mount_point='github'*)

Login using GitHub access token.

Supported methods: POST: /auth/{mount_point}/login. Produces: 200 application/json

Parameters

- **token** (*str | unicode*) – GitHub personal API token.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the *hvac.adapters.Adapter()* instance under the *_adapater* Client attribute.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the login request.

Return type dict

map_team (*team_name*, *policies=None*, *mount_point='github'*)

Map a list of policies to a team that exists in the configured GitHub organization.

Supported methods: POST: /auth/{mount_point}/map/teams/{team_name}. Produces: 204 (empty body)

Parameters

- **team_name** (*str | unicode*) – GitHub team name in “slugified” format
- **policies** (*List[str]*) – Comma separated list of policies to assign
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the map_github_teams request.

Return type requests.Response

map_user (*user_name*, *policies=None*, *mount_point='github'*)

Map a list of policies to a specific GitHub user exists in the configured organization.

Supported methods: POST: /auth/{mount_point}/map/users/{user_name}. Produces: 204 (empty body)

Parameters

- **user_name** (*str | unicode*) – GitHub user name
- **policies** (*List[str]*) – Comma separated list of policies to assign
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the map_github_users request.

Return type requests.Response

read_configuration (*mount_point='github'*)

Read the GitHub configuration.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_configuration request.

Return type dict

read_team_mapping (*team_name*, *mount_point*='github')

Read the GitHub team policy mapping.

Supported methods: GET: /auth/{mount_point}/map/teams/{team_name}. Produces: 200 application/json

Parameters

- **team_name** (*str* | *unicode*) – GitHub team name
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_team_mapping request.

Return type dict

read_user_mapping (*user_name*, *mount_point*='github')

Read the GitHub user policy mapping.

Supported methods: GET: /auth/{mount_point}/map/users/{user_name}. Produces: 200 application/json

Parameters

- **user_name** (*str* | *unicode*) – GitHub user name
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_user_mapping request.

Return type dict

class hvac.api.auth_methods.**Kubernetes** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

Kubernetes Auth Method (API).

Reference: <https://www.vaultproject.io/api/auth/kubernetes/index.html>

configure (*kubernetes_host*, *kubernetes_ca_cert*=None, *token_reviewer_jwt*=None, *pem_keys*=None, *mount_point*='kubernetes')

Configure the connection parameters for Kubernetes.

This path honors the distinction between the create and update capabilities inside ACL policies.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **kubernetes_host** (*str* | *unicode*) – Host must be a host string, a host:port pair, or a URL to the base of the Kubernetes API server. Example: https://k8s.example.com:443
- **kubernetes_ca_cert** (*str* | *unicode*) – PEM encoded CA cert for use by the TLS client used to talk with the Kubernetes API. NOTE: Every line must end with a newline:
- **token_reviewer_jwt** (*str* | *unicode*) – A service account JWT used to access the TokenReview API to validate other JWTs during login. If not set the JWT used for login will be used to access the API.

- **pem_keys** (*list*) – Optional list of PEM-formatted public keys or certificates used to verify the signatures of Kubernetes service account JWTs. If a certificate is given, its public key will be extracted. Not every installation of Kubernetes exposes these keys.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the `configure_method` request.

Return type `requests.Response`

create_role (*name, bound_service_account_names, bound_service_account_namespaces, ttl=None, max_ttl=None, period=None, policies=None, mount_point='kubernetes'*)

Create a role in the method.

Registers a role in the auth method. Role types have specific entities that can perform login operations against this endpoint. Constraints specific to the role type must be set on the role. These are applied to the authenticated entities attempting to login.

Supported methods: POST: `/auth/{mount_point}/role/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **bound_service_account_names** (*list | str | unicode*) – List of service account names able to access this role. If set to “*” all names are allowed, both this and `bound_service_account_namespaces` can not be “*”.
- **bound_service_account_namespaces** (*list | str | unicode*) – List of namespaces allowed to access this role. If set to “*” all namespaces are allowed, both this and `bound_service_account_names` can not be set to “*”.
- **ttl** (*str | unicode*) – The TTL period of tokens issued using this role in seconds.
- **max_ttl** (*str | unicode*) – The maximum allowed lifetime of tokens issued in seconds using this role.
- **period** (*str | unicode*) – If set, indicates that the token generated using this role should never expire. The token should be renewed within the duration specified by this value. At each renewal, the token’s TTL will be set to the value of this parameter.
- **policies** (*list | str | unicode*) – Policies to be set on tokens issued using this role.
- **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The response of the request.

Return type `requests.Response`

delete_role (*name, mount_point='kubernetes'*)

Delete the previously registered role.

Supported methods: DELETE: `/auth/{mount_point}/role/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the kubernetes auth method was mounted on.

Returns The response of the request.

Return type requests.Response

list_roles (*mount_point='kubernetes'*)

List all the roles that are registered with the plugin.

Supported methods: LIST: /auth/{mount_point}/role. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the kubernetes auth method was mounted on.

Returns The “data” key from the JSON response of the request.

Return type dict

login (*role, jwt, use_token=True, mount_point='kubernetes'*)

Fetch a token.

This endpoint takes a signed JSON Web Token (JWT) and a role name for some entity. It verifies the JWT signature to authenticate that entity and then authorizes the entity for the given role.

Supported methods: POST: /auth/{mount_point}/login. Produces: 200 application/json

Parameters

- **role** (*str | unicode*) – Name of the role against which the login is being attempted.
- **jwt** (*str | unicode*) – Signed JSON Web Token (JWT) from Azure MSI.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater Client` attribute.
- **mount_point** (*str | unicode*) – The “path” the azure auth method was mounted on.

Returns The JSON response of the request.

Return type dict

read_config (*mount_point='kubernetes'*)

Return the previously configured config, including credentials.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the kubernetes auth method was mounted on.

Returns The data key from the JSON response of the request.

Return type dict

read_role (*name, mount_point='kubernetes'*)

Returns the previously registered role configuration.

Supported methods: POST: /auth/{mount_point}/role/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the kubernetes auth method was mounted on.

Returns The “data” key from the JSON response of the request.

Return type dict

class hvac.api.auth_methods.Ldap (*adapter*)
 Bases: hvac.api.vault_api_base.VaultApiBase

LDAP Auth Method (API).

Reference: <https://www.vaultproject.io/api/auth/ldap/index.html>

configure (*user_dn=None, group_dn=None, url=None, case_sensitive_names=None, start-tls=None, tls_min_version=None, tls_max_version=None, insecure_tls=None, certificate=None, bind_dn=None, bind_pass=None, user_attr=None, discover_dn=None, deny_null_bind=True, upn_domain=None, group_filter=None, group_attr=None, mount_point='ldap'*)

Configure the LDAP auth method.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **user_dn** (*str | unicode*) – Base DN under which to perform user search. Example: ou=Users,dc=example,dc=com
- **group_dn** (*str | unicode*) – LDAP search base to use for group membership search. This can be the root containing either groups or users. Example: ou=Groups,dc=example,dc=com
- **url** (*str | unicode*) – The LDAP server to connect to. Examples: ldap://ldap.myorg.com, ldaps://ldap.myorg.com:636. Multiple URLs can be specified with commas, e.g. ldap://ldap.myorg.com,ldap://ldap2.myorg.com; these will be tried in-order.
- **case_sensitive_names** (*bool*) – If set, user and group names assigned to policies within the backend will be case sensitive. Otherwise, names will be normalized to lower case. Case will still be preserved when sending the username to the LDAP server at login time; this is only for matching local user/group definitions.
- **starttls** (*bool*) – If true, issues a StartTLS command after establishing an unencrypted connection.
- **tls_min_version** (*str | unicode*) – Minimum TLS version to use. Accepted values are tls10, tls11 or tls12.
- **tls_max_version** (*str | unicode*) – Maximum TLS version to use. Accepted values are tls10, tls11 or tls12.
- **insecure_tls** (*bool*) – If true, skips LDAP server SSL certificate verification - insecure, use with caution!
- **certificate** (*str | unicode*) – CA certificate to use when verifying LDAP server certificate, must be x509 PEM encoded.
- **bind_dn** (*str | unicode*) – Distinguished name of object to bind when performing user search. Example: cn=vault,ou=Users,dc=example,dc=com
- **bind_pass** (*str | unicode*) – Password to use along with binddn when performing user search.
- **user_attr** (*str | unicode*) – Attribute on user attribute object matching the username passed when authenticating. Examples: sAMAccountName, cn, uid
- **discover_dn** (*bool*) – Use anonymous bind to discover the bind DN of a user.

- **deny_null_bind** (*bool*) – This option prevents users from bypassing authentication when providing an empty password.
- **upn_domain** (*str | unicode*) – The userPrincipalDomain used to construct the UPN string for the authenticating user. The constructed UPN will appear as [username]@UPNDomain. Example: example.com, which will cause vault to bind as `username@example.com`.
- **group_filter** (*str | unicode*) – Go template used when constructing the group membership query. The template can access the following context variables: [UserDN, Username]. The default is `(!(memberUid={{.Username}})(member={{.UserDN}})(uniqueMember={{.UserDN}}))`, which is compatible with several common directory schemas. To support nested group resolution for Active Directory, instead use the following query: `(&(objectClass=group)(member:1.2.840.113556.1.4.1941:={{.UserDN}}))`.
- **group_attr** (*str | unicode*) – LDAP attribute to follow on objects returned by groupfilter in order to enumerate user group membership. Examples: for groupfilter queries returning group objects, use: cn. For queries returning user objects, use: memberOf. The default is cn.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the configure request.

Return type requests.Response

create_or_update_group (*name, policies=None, mount_point='ldap'*)

Create or update LDAP group policies.

Supported methods: POST: /auth/{mount_point}/groups/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name of the LDAP group
- **policies** (*list*) – List of policies associated with the group. This parameter is transformed to a comma-delimited string before being passed to Vault.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the create_or_update_group request.

Return type requests.Response

create_or_update_user (*username, policies=None, groups=None, mount_point='ldap'*)

Create or update LDAP users policies and group associations.

Supported methods: POST: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – The username of the LDAP user
- **policies** (*str | unicode*) – List of policies associated with the user. This parameter is transformed to a comma-delimited string before being passed to Vault.
- **groups** (*str | unicode*) – List of groups associated with the user. This parameter is transformed to a comma-delimited string before being passed to Vault.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the create_or_update_user request.

Return type requests.Response

delete_group (*name*, *mount_point='ldap'*)

Delete a LDAP group and policy association.

Supported methods: DELETE: /auth/{mount_point}/groups/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name of the LDAP group
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the delete_group request.

Return type requests.Response

delete_user (*username*, *mount_point='ldap'*)

Delete a LDAP user and policy association.

Supported methods: DELETE: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – The username of the LDAP user
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the delete_user request.

Return type requests.Response

list_groups (*mount_point='ldap'*)

List existing LDAP existing groups that have been created in this auth method.

Supported methods: LIST: /auth/{mount_point}/groups. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the list_groups request.

Return type dict

list_users (*mount_point='ldap'*)

List existing users in the method.

Supported methods: LIST: /auth/{mount_point}/users. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the list_users request.

Return type dict

login (*username*, *password*, *use_token=True*, *mount_point='ldap'*)

Log in with LDAP credentials.

Supported methods: POST: /auth/{mount_point}/login/{username}. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – The username of the LDAP user
- **password** (*str | unicode*) – The password for the LDAP user
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the `login_with_user` request.

Return type `requests.Response`

read_configuration (*mount_point='ldap'*)

Retrieve the LDAP configuration for the auth method.

Supported methods: GET: `/auth/{mount_point}/config`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_configuration` request.

Return type `dict`

read_group (*name, mount_point='ldap'*)

Read policies associated with a LDAP group.

Supported methods: GET: `/auth/{mount_point}/groups/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – The name of the LDAP group
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_group` request.

Return type `dict`

read_user (*username, mount_point='ldap'*)

Read policies associated with a LDAP user.

Supported methods: GET: `/auth/{mount_point}/users/{username}`. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – The username of the LDAP user
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_user` request.

Return type `dict`

class `hvac.api.auth_methods.Userpass` (*adapter*)

Bases: `hvac.api.vault_api_base.VaultApiBase`

USERPASS Auth Method (API). Reference: <https://www.vaultproject.io/api/auth/userpass/index.html>

create_or_update_user (*username, password, mount_point='userpass'*)

Create/update user in userpass.

Supported methods: POST: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – The username for the user.
- **password** (*str | unicode*) – The password for the user. Only required when creating the user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

delete_user (*username, mount_point='userpass'*)

Delete user in the auth method.

Supported methods: GET: /auth/{mount_point}/users/{username}. Produces: 200 application/json

Parameters

- **username** – The username for the user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_group request.

Return type dict

list_user (*mount_point='userpass'*)

List existing users that have been created in the auth method

Supported methods: LIST: /auth/{mount_point}/users. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the list_groups request.

Return type dict

login (*username, password, mount_point='userpass'*)

Log in with USERPASS credentials.

Supported methods: POST: /auth/{mount_point}/login/{username}. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – The username for the user.
- **password** (*str | unicode*) – The password for the user. Only required when creating the user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

read_user (*username, mount_point='userpass'*)

Read user in the auth method.

Supported methods: GET: /auth/{mount_point}/users/{username}. Produces: 200 application/json

Parameters

- **username** – The username for the user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_group` request.

Return type dict

update_password_on_user (*username, password, mount_point='userpass'*)
update password for the user in `userpass`.

Supported methods: POST: `/auth/{mount_point}/users/{username}/password`. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – The username for the user.
- **password** (*str | unicode*) – The password for the user. Only required when creating the user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

class `hvac.api.auth_methods.Mfa` (*adapter*)
Bases: `hvac.api.vault_api_base.VaultApiBase`
Multi-factor authentication Auth Method (API).

Warning: This class’s methods correspond to a legacy / unsupported set of Vault API routes. Please see the reference link for additional context.

Reference: <https://www.vaultproject.io/docs/auth/mfa.html>

configure (*mount_point, mfa_type='duo', force=False*)
Configure MFA for a supported method.

This endpoint allows you to turn on multi-factor authentication with a given backend. Currently only Duo is supported.

Supported methods: POST: `/auth/{mount_point}/mfa_config`. Produces: 204 (empty body)

Parameters

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.
- **mfa_type** (*str | unicode*) – Enables MFA with given backend (available: duo)
- **force** (*bool*) – If True, make the “mfa_config” request regardless of circumstance. If False (the default), verify the provided `mount_point` is available and one of the types of methods supported by this feature.

Returns The response of the configure MFA request.

Return type requests.Response

configure_duo_access (*mount_point, host, integration_key, secret_key*)
Configure the access keys and host for Duo API connections.

To authenticate users with Duo, the backend needs to know what host to connect to and must authenticate with an integration key and secret key. This endpoint is used to configure that information.

Supported methods: POST: `/auth/{mount_point}/duo/access`. Produces: 204 (empty body)

Parameters

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.
- **host** (*str | unicode*) – Duo API host
- **integration_key** (*Duo secret key*) – Duo integration key
- **secret_key** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the `configure_duo_access` request.

Return type `requests.Response`

configure_duo_behavior (*mount_point*, *push_info=None*, *user_agent=None*, *username_format='%s'*)

Configure Duo second factor behavior.

This endpoint allows you to configure how the original auth method username maps to the Duo username by providing a template format string.

Supported methods: POST: `/auth/{mount_point}/duo/config`. Produces: 204 (empty body)

Parameters

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.
- **push_info** (*str | unicode*) – A string of URL-encoded key/value pairs that provides additional context about the authentication attempt in the Duo Mobile app
- **user_agent** (*str | unicode*) – User agent to connect to Duo (default “”)
- **username_format** (*str | unicode*) – Format string given auth method username as argument to create Duo username (default ‘%s’)

Returns The response of the `configure_duo_behavior` request.

Return type `requests.Response`

read_configuration (*mount_point*)

Read the MFA configuration.

Supported methods: GET: `/auth/{mount_point}/mfa_config`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_configuration` request.

Return type `dict`

read_duo_behavior_configuration (*mount_point*)

Read the Duo second factor behavior configuration.

Supported methods: GET: `/auth/{mount_point}/duo/config`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the `read_duo_behavior_configuration` request.

Return type `dict`

class hvac.api.auth_methods.Okta (*adapter*)
 Bases: hvac.api.vault_api_base.VaultApiBase

Okta Auth Method (API).

Reference: <https://www.vaultproject.io/api/auth/okta/index.html>

configure (*org_name*, *api_token=None*, *base_url=None*, *ttl=None*, *max_ttl=None*, *bypass_okta_mfa=None*, *mount_point='okta'*)
 Configure the connection parameters for Okta.

This path honors the distinction between the create and update capabilities inside ACL policies.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **org_name** (*str | unicode*) – Name of the organization to be used in the Okta API.
- **api_token** (*str | unicode*) – Okta API token. This is required to query Okta for user group membership. If this is not supplied only locally configured groups will be enabled.
- **base_url** (*str | unicode*) – If set, will be used as the base domain for API requests. Examples are okta.com, oktapreview.com, and okta-emea.com.
- **ttl** (*str | unicode*) – Duration after which authentication will be expired.
- **max_ttl** (*str | unicode*) – Maximum duration after which authentication will be expired.
- **bypass_okta_mfa** (*bool*) – Whether to bypass an Okta MFA request. Useful if using one of Vault’s built-in MFA mechanisms, but this will also cause certain other statuses to be ignored, such as PASSWORD_EXPIRED.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_group (*name*, *mount_point='okta'*)
 Delete an existing group from the method.

Supported methods: DELETE: /auth/{mount_point}/groups/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name for the group.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_user (*username*, *mount_point='okta'*)
 Delete an existing username from the method.

Supported methods: DELETE: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – Username for this user.

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

list_groups (*mount_point='okta'*)

List the groups configured in the Okta method.

Supported methods: LIST: /auth/{mount_point}/groups. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_users (*mount_point='okta'*)

List the users configured in the Okta method.

Supported methods: LIST: /auth/{mount_point}/users. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

login (*username, password, use_token=True, mount_point='okta'*)

Login with the username and password.

Supported methods: POST: /auth/{mount_point}/login/{username}. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – Username for this user.
- **password** (*str | unicode*) – Password for the authenticating user.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the *hvac.adapters.Adapter()* instance under the *_adapater* Client attribute.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the login request.

Return type dict

read_config (*mount_point='okta'*)

Read the Okta configuration.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_group (*name*, *mount_point='okta'*)

Read the properties of an existing group.

Supported methods: GET: /auth/{mount_point}/groups/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – The name for the group.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_user (*username*, *mount_point='okta'*)

Read the properties of an existing username.

Supported methods: GET: /auth/{mount_point}/users/{username}. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – Username for this user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

register_group (*name*, *policies=None*, *mount_point='okta'*)

Register a new group and maps a set of policies to it.

Supported methods: POST: /auth/{mount_point}/groups/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – The name of the group.
- **policies** (*list*) – The list or comma-separated string of policies associated with the group.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

register_user (*username*, *groups=None*, *policies=None*, *mount_point='okta'*)

Register a new user and maps a set of policies to it.

Supported methods: POST: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – Name of the user.
- **groups** (*list*) – List or comma-separated string of groups associated with the user.
- **policies** (*list*) – List or comma-separated string of policies associated with the user.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

class hvac.api.auth_methods.**Radius** (*adapter*)
 Bases: hvac.api.vault_api_base.VaultApiBase

RADIUS Auth Method (API).

Reference: <https://www.vaultproject.io/docs/auth/radius.html>

configure (*host, secret, port=None, unregistered_user_policies=None, dial_timeout=None, nas_port=None, mount_point='radius'*)
 Configure the RADIUS auth method.

Supported methods: POST: /auth/{mount_point}/config. Produces: 204 (empty body)

Parameters

- **host** (*str | unicode*) – The RADIUS server to connect to. Examples: radius.myorg.com, 127.0.0.1
- **secret** (*str | unicode*) – The RADIUS shared secret.
- **port** (*int*) – The UDP port where the RADIUS server is listening on. Defaults is 1812.
- **unregistered_user_policies** (*list*) – A comma-separated list of policies to be granted to unregistered users.
- **dial_timeout** (*int*) – Number of second to wait for a backend connection before timing out. Default is 10.
- **nas_port** (*int*) – The NAS-Port attribute of the RADIUS request. Defaults is 10.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the configure request.

Return type requests.Response

delete_user (*username, mount_point='radius'*)
 Delete a RADIUS user and policy association.

Supported methods: DELETE: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – The username of the RADIUS user
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the delete_user request.

Return type requests.Response

list_users (*mount_point='radius'*)
 List existing users in the method.

Supported methods: LIST: /auth/{mount_point}/users. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the list_users request.

Return type dict

login (*username, password, use_token=True, mount_point='radius'*)

Log in with RADIUS credentials.

Supported methods: POST: /auth/{mount_point}/login/{username}. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – The username of the RADIUS user
- **password** (*str | unicode*) – The password for the RADIUS user
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the login_with_user request.

Return type requests.Response

read_configuration (*mount_point='radius'*)

Retrieve the RADIUS configuration for the auth method.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_configuration request.

Return type dict

read_user (*username, mount_point='radius'*)

Read policies associated with a RADIUS user.

Supported methods: GET: /auth/{mount_point}/users/{username}. Produces: 200 application/json

Parameters

- **username** (*str | unicode*) – The username of the RADIUS user
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_user request.

Return type dict

register_user (*username, policies=None, mount_point='radius'*)

Create or update RADIUS user with a set of policies.

Supported methods: POST: /auth/{mount_point}/users/{username}. Produces: 204 (empty body)

Parameters

- **username** (*str | unicode*) – Username for this RADIUS user.
- **policies** (*list*) – List of policies associated with the user. This parameter is transformed to a comma-delimited string before being passed to Vault.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the register_user request.

Return type requests.Response

class hvac.api.auth_methods.**Aws** (*adapter*)
 Bases: hvac.api.vault_api_base.VaultApiBase

AWS Auth Method (API).

Reference: <https://www.vaultproject.io/api/auth/aws/index.html>

configure (*max_retries=None, access_key=None, secret_key=None, endpoint=None, iam_endpoint=None, sts_endpoint=None, iam_server_id_header_value=None, mount_point='aws'*)

Configures the credentials required to perform API calls to AWS as well as custom endpoints to talk to AWS API

The instance identity document fetched from the PKCS#7 signature will provide the EC2 instance ID. The credentials configured using this endpoint will be used to query the status of the instances via DescribeInstances API. If static credentials are not provided using this endpoint, then the credentials will be retrieved from the environment variables AWS_ACCESS_KEY, AWS_SECRET_KEY and AWS_REGION respectively. If the credentials are still not found and if the method is configured on an EC2 instance with metadata querying capabilities, the credentials are fetched automatically

Supported methods: POST: /auth/{mount_point}/config Produces: 204 (empty body)

Parameters

- **max_retries** (*int*) – Number of max retries the client should use for recoverable errors. The default (-1) falls back to the AWS SDK’s default behavior
- **access_key** (*str | unicode*) – AWS Access key with permissions to query AWS APIs. The permissions required depend on the specific configurations. If using the iam auth method without inferencing, then no credentials are necessary. If using the ec2 auth method or using the iam auth method with inferencing, then these credentials need access to ec2:DescribeInstances. If additionally a bound_iam_role is specified, then these credentials also need access to iam:GetInstanceProfile. If, however, an alternate sts configuration is set for the target account, then the credentials must be permissioned to call sts:AssumeRole on the configured role, and that role must have the permissions described here
- **secret_key** (*str | unicode*) – AWS Secret key with permissions to query AWS APIs
- **endpoint** (*str | unicode*) – URL to override the default generated endpoint for making AWS EC2 API calls
- **iam_endpoint** (*str | unicode*) – URL to override the default generated endpoint for making AWS IAM API calls
- **sts_endpoint** (*str | unicode*) – URL to override the default generated endpoint for making AWS STS API calls
- **iam_server_id_header_value** (*str | unicode*) – The value to require in the X-Vault-AWS-IAM-Server-ID header as part of GetCallerIdentity requests that are used in the iam auth method. If not set, then no value is required or validated. If set, clients must include an X-Vault-AWS-IAM-Server-ID header in the headers of login requests, and further this header must be among the signed headers validated by AWS. This is to protect against different types of replay attacks, for example a signed request sent to a dev server being resent to a production server
- **mount_point** (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request.

Return type requests.Response

configure_identity_integration (*iam_alias=None, ec2_alias=None, mount_point='aws'*)

Configures the way that Vault interacts with the Identity store. The default (as of Vault 1.0.3) is role_id for both values

Supported methods: POST: /auth/{mount_point}/config/identity Produces: 204 (empty body)

Parameters

- **iam_alias** (*str | unicode*) – How to generate the identity alias when using the iam auth method. Valid choices are role_id, unique_id, and full_arn. When role_id is selected, the randomly generated ID of the role is used. When unique_id is selected, the IAM Unique ID of the IAM principal (either the user or role) is used as the identity alias name. When full_arn is selected, the ARN returned by the sts:GetCallerIdentity call is used as the alias name. This is either arn:aws:iam::<account_id>:user/<optional_path/><user_name> or arn:aws:sts::<account_id>:assumed-role/<role_name_without_path/><role_session_name>. Note: if you select full_arn and then delete and recreate the IAM role, Vault won't be aware and any identity aliases set up for the role name will still be valid
- **ec2_alias** (*str | unicode*) – Configures how to generate the identity alias when using the ec2 auth method. Valid choices are role_id, instance_id, and image_id. When role_id is selected, the randomly generated ID of the role is used. When instance_id is selected, the instance identifier is used as the identity alias name. When image_id is selected, AMI ID of the instance is used as the identity alias name
- **mount_point** (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request

Return type request.Response

configure_identity_whitelist_tidy (*safety_buffer=None, disable_periodic_tidy=None, mount_point='aws'*)

Configures the periodic tidying operation of the whitelisted identity entries

Parameters

- **safety_buffer** –
- **disable_periodic_tidy** –
- **mount_point** –

Returns

configure_role_tag_blacklist_tidy (*safety_buffer=None, disable_periodic_tidy=None, mount_point='aws'*)

Configures the periodic tidying operation of the blacklisted role tag entries

Parameters

- **safety_buffer** –
- **disable_periodic_tidy** –
- **mount_point** –

Returns

create_certificate_configuration (*cert_name*, *aws_public_cert*, *document_type=*None,
mount_point='aws')

Registers an AWS public key to be used to verify the instance identity documents

While the PKCS#7 signature of the identity documents have DSA digest, the identity signature will have RSA digest, and hence the public keys for each type varies respectively. Indicate the type of the public key using the “type” parameter

Supported methods: POST: /auth/{mount_point}/config/certificate/:cert_name Produces: 204 (empty body)

Parameters

- **cert_name** (*string | unicode*) – Name of the certificate
- **aws_public_cert** – Base64 encoded AWS Public key required to verify PKCS7 signature of the EC2 instance metadata
- **document_type** (*string | unicode*) – Takes the value of either “pkcs7” or “identity”, indicating the type of document which can be verified using the given certificate
- **mount_point** (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request

Return type request.Response

create_role (*role*, *auth_type=*None, *bound_ami_id=*None, *bound_account_id=*None,
*bound_region=*None, *bound_vpc_id=*None, *bound_subnet_id=*None,
*bound_iam_role_arn=*None, *bound_iam_instance_profile_arn=*None,
*bound_ec2_instance_id=*None, *role_tag=*None, *bound_iam_principal_arn=*None, *inferred_entity_type=*None, *inferred_aws_region=*None, *resolve_aws_unique_ids=*None,
*ttl=*None, *max_ttl=*None, *period=*None, *policies=*None, *allow_instance_migration=*None,
*disallow_reauthentication=*None,
mount_point='aws')

Registers a role in the method. Only those instances or principals which are using the role registered using this endpoint, will be able to perform the login operation

Constraints can be specified on the role, that are applied on the instances or principals attempting to login. At least one constraint must be specified on the role. The available constraints you can choose are dependent on the *auth_type* of the role and, if the *auth_type* is iam, then whether inferencing is enabled. A role will not let you configure a constraint if it is not checked by the *auth_type* and inferencing configuration of that role. For the constraints which accept a list of values, the authenticating instance/principal must match any one value in the list in order to satisfy that constraint

Parameters

- **role** –
- **auth_type** –
- **bound_ami_id** –
- **bound_account_id** –
- **bound_region** –
- **bound_vpc_id** –
- **bound_subnet_id** –
- **bound_iam_role_arn** –

- `bound_iam_instance_profile_arn` -
- `bound_ec2_instance_id` -
- `role_tag` -
- `bound_iam_principal_arn` -
- `inferred_entity_type` -
- `inferred_aws_region` -
- `resolve_aws_unique_ids` -
- `ttl` -
- `max_ttl` -
- `period` -
- `policies` -
- `allow_instance_migration` -
- `disallow_reauthentication` -
- `mount_point` -

Returns

`create_role_tags` (*role*, *policies=None*, *max_ttl=None*, *instance_id=None*, *allow_instance_migration=None*, *disallow_reauthentication=None*, *mount_point='aws'*)

Creates a role tag on the role, which helps in restricting the capabilities that are set on the role. Role tags are not tied to any specific ec2 instance unless specified explicitly using the `instance_id` parameter

Role tags are not tied to any specific ec2 instance unless specified explicitly using the `instance_id` parameter. By default, role tags are designed to be used across all instances that satisfies the constraints on the role. Regardless of which instances have role tags on them, capabilities defined in a role tag must be a strict subset of the given role's capabilities. Note that, since adding and removing a tag is often a widely distributed privilege, care needs to be taken to ensure that the instances are attached with correct tags to not let them gain more privileges than what were intended. If a role tag is changed, the capabilities inherited by the instance will be those defined on the new role tag. Since those must be a subset of the role capabilities, the role should never provide more capabilities than any given instance can be allowed to gain in a worst-case scenario

Parameters

- `role` -
- `policies` -
- `max_ttl` -
- `instance_id` -
- `allow_instance_migration` -
- `disallow_reauthentication` -
- `mount_point` -

Returns

`create_sts_role` (*account_id*, *sts_role*, *mount_point='aws'*)

Allows the explicit association of STS roles to satellite AWS accounts (i.e. those which are not the account in which the Vault server is running.)

Vault will use credentials obtained by assuming these STS roles when validating IAM principals or EC2 instances in the particular AWS account

Supported methods: POST: `/v1/auth/{mount_point}/config/sts/:account_id` Produces: 204 (empty body)

Parameters

- `account_id` –
- `sts_role` –
- `mount_point` –

Returns

`delete_blacklist_tags` (*role_tag, mount_point='aws'*)

Deletes a blacklisted role tag

Parameters

- `role_tag` –
- `mount_point` –

Returns

`delete_certificate_configuration` (*cert_name, mount_point='aws'*)

Removes the previously configured AWS public key

Supported methods: DELETE: `/auth/{mount_point}/config/certificate/:cert_name` Produces: 204 (empty body)

Parameters

- `cert_name` (*str | unicode*) – Name of the certificate
- `mount_point` (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request

Return type request.Response

`delete_config` (*mount_point='aws'*)

Deletes the previously configured AWS access credentials

Supported methods: DELETE: `/auth/{mount_point}/config` Produces: 204 (empty body)

Parameters `mount_point` (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The response of the request.

Return type requests.Response

`delete_identity_whitelist_entries` (*instance_id, mount_point='aws'*)

Deletes a cache of the successful login from an instance

Parameters

- `instance_id` –

- `mount_point` –

Returns

`delete_identity_whitelist_tidy` (*mount_point='aws'*)

Deletes the previously configured periodic whitelist tidying settings

Parameters `mount_point` –

Returns

`delete_role` (*role, mount_point='aws'*)

Deletes the previously registered role

Parameters

- `role` –
- `mount_point` –

Returns

`delete_role_tag_blacklist_tidy` (*mount_point='aws'*)

Deletes the previously configured periodic blacklist tidying settings

Parameters `mount_point` –

Returns

`delete_sts_role` (*account_id, mount_point='aws'*)

Deletes a previously configured AWS account/STS role association

Parameters

- `account_id` –
- `mount_point` –

Returns

`ec2_login` (*pkcs7, nonce=None, role=None, use_token=True, mount_point='aws'*)

Fetch a token :param pkcs7: :param nonce: :param role: :param use_token: :param mount_point:

`iam_login` (*access_key, secret_key, session_token=None, header_value=None, role=None, use_token=True, region='us-east-1', mount_point='aws'*)

Fetch a token

This endpoint verifies the pkcs7 signature of the instance identity document or the signature of the signed GetCallerIdentity request. With the ec2 auth method, or when inferring an EC2 instance, verifies that the instance is actually in a running state. Cross checks the constraints defined on the role with which the login is being performed. With the ec2 auth method, as an alternative to pkcs7 signature, the identity document along with its RSA digest can be supplied to this endpoint

Parameters `mount_point` –

Returns

`list_blacklist_tags` (*mount_point='aws'*)

Lists all the role tags that are blacklisted

Parameters `mount_point` –

Returns

`list_certificate_configurations` (*mount_point='aws'*)

Lists all the AWS public certificates that are registered with the method

Supported methods LIST: /auth/{mount_point}/config/certificates Produces: 200 application/json

Parameters `mount_point` –

Returns

list_identity_whitelist (*mount_point='aws'*)

Lists all the instance IDs that are in the whitelist of successful logins

Parameters `mount_point` –

Returns

list_roles (*mount_point='aws'*)

Lists all the roles that are registered with the method

Parameters `mount_point` –

Returns

list_sts_roles (*mount_point='aws'*)

Lists all the AWS Account IDs for which an STS role is registered

Parameters `mount_point` –

Returns

place_role_tags_in_blacklist (*role_tag, mount_point='aws'*)

Places a valid role tag in a blacklist

This ensures that the role tag cannot be used by any instance to perform a login operation again. Note that if the role tag was previously used to perform a successful login, placing the tag in the blacklist does not invalidate the already issued token

Parameters

- `role_tag` –
- `mount_point` –

Returns

read_certificate_configuration (*cert_name, mount_point='aws'*)

Returns the previously configured AWS public key

Supported methods: GET: /v1/auth/{mount_point}/config/certificate/:cert_name Produces: 200 application/json

Parameters

- `cert_name` (*str | unicode*) – Name of the certificate
- `mount_point` – The “path” the aws auth method was mounted on

Returns The data key from the JSON response of the request.

Return type dict

read_config (*mount_point='aws'*)

Returns the previously configured AWS access credentials

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The data key from the JSON response of the request.

Return type dict

read_identity_integration (*mount_point='aws'*)

Returns the previously configured identity integration configuration

Supported methods: GET: /auth/{mount_point}/config/identity. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the aws auth method was mounted on

Returns The data key from the JSON response of the request.

Return type dict

read_identity_whitelist (*instance_id, mount_point='aws'*)

Returns an entry in the whitelist. An entry will be created/updated by every successful login

Parameters

- `instance_id` –
- `mount_point` –

Returns

read_identity_whitelist_tidy (*mount_point='aws'*)

Returns the previously configured periodic whitelist tidying settings

Parameters `mount_point` –

Returns

read_role (*role, mount_point='aws'*)

Returns the previously registered role configuration

Parameters

- `role` –
- `mount_point` –

Returns

read_role_tag_blacklist (*role_tag, mount_point='aws'*)

Returns the blacklist entry of a previously blacklisted role tag

Parameters

- `role_tag` –
- `mount_point` –

Returns

read_role_tag_blacklist_tidy (*mount_point='aws'*)

Returns the previously configured periodic blacklist tidying settings

Parameters `mount_point` –

Returns

read_sts_role (*account_id*, *mount_point*='aws')

Returns the previously configured STS role

Parameters

- **account_id** –
- **mount_point** –

Returns

tidy_blacklist_tags (*saftey_buffer*='72h', *mount_point*='aws')

Cleans up the entries in the blacklist based on expiration time on the entry and *safety_buffer*

Parameters

- **saftey_buffer** –
- **mount_point** –

Returns

tidy_identity_whitelist_entries (*saftey_buffer*='72h', *mount_point*='aws')

Cleans up the entries in the whitelist based on expiration time and *safety_buffer*

Parameters

- **saftey_buffer** –
- **mount_point** –

Returns

4.4 hvac.api.secrets_engines

Vault secrets engines endpoints

class hvac.api.secrets_engines.**Aws** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

AWS Secrets Engine (API).

Reference: <https://www.vaultproject.io/api/secret/aws/index.html>

configure_lease (*lease*, *lease_max*, *mount_point*='aws')

Configure lease settings for the AWS secrets engine.

It is optional, as there are default values for *lease* and *lease_max*.

Supported methods: POST: `/{mount_point}/config/lease`. Produces: 204 (empty body)

Parameters

- **lease** (*str* | *unicode*) – Specifies the lease value provided as a string duration with time suffix. “h” (hour) is the largest suffix.
- **lease_max** (*str* | *unicode*) – Specifies the maximum lease value provided as a string duration with time suffix. “h” (hour) is the largest suffix.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

configure_root_iam_credentials (*access_key*, *secret_key*, *region=None*,
iam_endpoint=None, *sts_endpoint=None*,
max_retries=None, *mount_point='aws'*)

Configure the root IAM credentials to communicate with AWS.

There are multiple ways to pass root IAM credentials to the Vault server, specified below with the highest precedence first. If credentials already exist, this will overwrite them.

The official AWS SDK is used for sourcing credentials from env vars, shared files, or IAM/ECS instances.

- Static credentials provided to the API as a payload
- Credentials in the `AWS_ACCESS_KEY`, `AWS_SECRET_KEY`, and `AWS_REGION` environment variables on the server
- Shared credentials files
- Assigned IAM role or ECS task role credentials

At present, this endpoint does not confirm that the provided AWS credentials are valid AWS credentials with proper permissions.

Supported methods: POST: `/{{mount_point}}/config/root`. Produces: 204 (empty body)

Parameters

- **access_key** (*str | unicode*) – Specifies the AWS access key ID.
- **secret_key** (*str | unicode*) – Specifies the AWS secret access key.
- **region** (*str | unicode*) – Specifies the AWS region. If not set it will use the `AWS_REGION` env var, `AWS_DEFAULT_REGION` env var, or `us-east-1` in that order.
- **iam_endpoint** (*str | unicode*) – Specifies a custom HTTP IAM endpoint to use.
- **sts_endpoint** (*str | unicode*) – Specifies a custom HTTP STS endpoint to use.
- **max_retries** (*int*) – Number of max retries the client should use for recoverable errors. The default (-1) falls back to the AWS SDK's default behavior.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

create_or_update_role (*name*, *credential_type*, *policy_document=None*, *default_sts_ttl=None*,
max_sts_ttl=None, *role_arns=None*, *policy_arns=None*,
legacy_params=False, *mount_point='aws'*)

Create or update the role with the given name.

If a role with the name does not exist, it will be created. If the role exists, it will be updated with the new attributes.

Supported methods: POST: `/{{mount_point}}/roles/{{name}}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to create. This is part of the request URL.
- **credential_type** (*str | unicode*) – Specifies the type of credential to be used when retrieving credentials from the role. Must be one of `iam_user`, `assumed_role`, or `federation_token`.

- **policy_document** (*dict | str | unicode*) – The IAM policy document for the role. The behavior depends on the credential type. With `iam_user`, the policy document will be attached to the IAM user generated and augment the permissions the IAM user has. With `assumed_role` and `federation_token`, the policy document will act as a filter on what the credentials can do.
- **default_sts_ttl** (*str | unicode*) – The default TTL for STS credentials. When a TTL is not specified when STS credentials are requested, and a default TTL is specified on the role, then this default TTL will be used. Valid only when `credential_type` is one of `assumed_role` or `federation_token`.
- **max_sts_ttl** (*str | unicode*) – The max allowed TTL for STS credentials (credentials TTL are capped to `max_sts_ttl`). Valid only when `credential_type` is one of `assumed_role` or `federation_token`.
- **role_arns** (*list | str | unicode*) – Specifies the ARNs of the AWS roles this Vault role is allowed to assume. Required when `credential_type` is `assumed_role` and prohibited otherwise. This is a comma-separated string or JSON array. String types supported for Vault legacy parameters.
- **policy_arns** (*list*) – Specifies the ARNs of the AWS managed policies to be attached to IAM users when they are requested. Valid only when `credential_type` is `iam_user`. When `credential_type` is `iam_user`, at least one of `policy_arns` or `policy_document` must be specified. This is a comma-separated string or JSON array.
- **legacy_params** (*bool*) – Flag to send legacy (Vault versions < 0.11.0) parameters in the request. When this is set to `True`, `policy_document` and `policy_arns` are the only parameters used from this method.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

delete_role (*name, mount_point='aws'*)

Delete an existing role by the given name.

If the role does not exist, a 404 is returned.

Supported methods: DELETE: `/{{mount_point}}/roles/{{name}}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – the name of the role to delete. This is part of the request URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

generate_credentials (*name, role_arn=None, ttl=None, endpoint='creds', mount_point='aws'*)

Generates credential based on the named role.

This role must be created before queried.

The `/aws/creds` and `/aws/sts` endpoints are almost identical. The exception is when retrieving credentials for a role that was specified with the legacy `arn` or `policy` parameter. In this case, credentials retrieved through `/aws/sts` must be of either the `assumed_role` or `federation_token` types, and credentials retrieved through `/aws/creds` must be of the `iam_user` type.

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to generate credentials against. This is part of the request URL.
- **role_arn** (*str | unicode*) – The ARN of the role to assume if `credential_type` on the Vault role is `assumed_role`. Must match one of the allowed role ARNs in the Vault role. Optional if the Vault role only allows a single AWS role ARN; required otherwise.
- **ttl** (*str | unicode*) – Specifies the TTL for the use of the STS token. This is specified as a string with a duration suffix. Valid only when `credential_type` is `assumed_role` or `federation_token`. When not specified, the default `sts_ttl` set for the role will be used. If that is also not set, then the default value of 3600s will be used. AWS places limits on the maximum TTL allowed. See the AWS documentation on the `DurationSeconds` parameter for `AssumeRole` (for `assumed_role` credential types) and `GetFederationToken` (for `federation_token` credential types) for more details.
- **endpoint** (*str | unicode*) – Supported endpoints: GET: `/{mount_point}/creds/{name}`. Produces: 200 application/json GET: `/{mount_point}/sts/{name}`. Produces: 200 application/json
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_roles (*mount_point='aws'*)

List all existing roles in the secrets engine.

Supported methods: LIST: `/{mount_point}/roles`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_lease_config (*mount_point='aws'*)

Read the current lease settings for the AWS secrets engine.

Supported methods: GET: `/{mount_point}/config/lease`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_role (*name, mount_point='aws'*)

Query an existing role by the given name.

If the role does not exist, a 404 is returned.

Supported methods: GET: `/{mount_point}/roles/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to read. This is part of the request URL.

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

rotate_root_iam_credentials (*mount_point='aws'*)

Rotate static root IAM credentials.

When you have configured Vault with static credentials, you can use this endpoint to have Vault rotate the access key it used. Note that, due to AWS eventual consistency, after calling this endpoint, subsequent calls from Vault to AWS may fail for a few seconds until AWS becomes consistent again.

In order to call this endpoint, Vault’s AWS access key **MUST** be the only access key on the IAM user; otherwise, generation of a new access key will fail. Once this method is called, Vault will now be the only entity that knows the AWS secret key is used to access AWS.

Supported methods: POST: `/{{mount_point}}/config/rotate-root`. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

class `hvac.api.secrets_engines.Azure` (*adapter*)

Bases: `hvac.api.vault_api_base.VaultApiBase`

Azure Secrets Engine (API).

Reference: <https://www.vaultproject.io/api/secret/azure/index.html>

configure (*subscription_id, tenant_id, client_id=None, client_secret=None, environment=None, mount_point='azure'*)

Configure the credentials required for the plugin to perform API calls to Azure.

These credentials will be used to query roles and create/delete service principals. Environment variables will override any parameters set in the config.

Supported methods: POST: `/{{mount_point}}/config`. Produces: 204 (empty body)

Parameters

- **subscription_id** (*str | unicode*) – The subscription id for the Azure Active Directory
- **tenant_id** (*str | unicode*) – The tenant id for the Azure Active Directory.
- **client_id** (*str | unicode*) – The OAuth2 client id to connect to Azure.
- **client_secret** (*str | unicode*) – The OAuth2 client secret to connect to Azure.
- **environment** (*str | unicode*) – The Azure environment. If not specified, Vault will use Azure Public Cloud.
- **mount_point** (*str | unicode*) – The OAuth2 client secret to connect to Azure.

Returns The response of the request.

Return type `requests.Response`

create_or_update_role (*name, azure_roles, ttl=None, max_ttl=None, mount_point='azure'*)

Create or update a Vault role.

The provided Azure roles must exist for this call to succeed. See the Azure secrets roles docs for more information about roles.

Supported methods: POST: `/mount_point/roles/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **azure_roles** (*list(dict)*) – List of Azure roles to be assigned to the generated service principal.
- **ttl** (*str | unicode*) – Specifies the default TTL for service principals generated using this role. Accepts time suffixed strings (“1h”) or an integer number of seconds. Defaults to the system/engine default TTL time.
- **max_ttl** (*str | unicode*) – Specifies the maximum TTL for service principals generated using this role. Accepts time suffixed strings (“1h”) or an integer number of seconds. Defaults to the system/engine max TTL time.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_config (*mount_point='azure'*)

Delete the stored Azure configuration and credentials.

Supported methods: DELETE: `/auth/{mount_point}/config`. Produces: 204 (empty body)

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

generate_credentials (*name, mount_point='azure'*)

Generate a new service principal based on the named role.

Supported methods: GET: `/mount_point/creds/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to create credentials against.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the request.

Return type dict

list_roles (*mount_point='azure'*)

List all of the roles that are registered with the plugin.

Supported methods: LIST: `/mount_point/roles`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the request.

Return type dict

read_config (*mount_point='azure'*)

Read the stored configuration, omitting `client_secret`.

Supported methods: GET: `/{{mount_point}}/config`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The data key from the JSON response of the request.

Return type dict

class `hvac.api.secrets_engines.Gcp` (*adapter*)

Bases: `hvac.api.vault_api_base.VaultApiBase`

Google Cloud Secrets Engine (API).

Reference: <https://www.vaultproject.io/api/secret/gcp/index.html>

configure (*credentials=None, ttl=None, max_ttl=None, mount_point='gcp'*)

Configure shared information for the Gcp secrets engine.

Supported methods: POST: `/{{mount_point}}/config`. Produces: 204 (empty body)

Parameters

- **credentials** (*str | unicode*) – JSON credentials (either file contents or ‘@path/to/file’) See docs for alternative ways to pass in to this parameter, as well as the required permissions.
- **ttl** (*int | str*) – Specifies default config TTL for long-lived credentials (i.e. service account keys). Accepts integer number of seconds or Go duration format string.
- **max_ttl** (*int | str*) – Specifies the maximum config TTL for long-lived credentials (i.e. service account keys). Accepts integer number of seconds or Go duration format string.**
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

create_or_update_roleset (*name, project, bindings, secret_type=None, token_scopes=None, mount_point='gcp'*)

Create a roleset or update an existing roleset.

See roleset docs for the GCP secrets backend to learn more about what happens when you create or update a roleset.

Supported methods: POST: `/{{mount_point}}/roleset/{{name}}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role. Cannot be updated.
- **project** (*str | unicode*) – Name of the GCP project that this roleset’s service account will belong to. Cannot be updated.
- **bindings** (*str | unicode*) – Bindings configuration string (expects HCL or JSON format in raw or base64-encoded string)
- **secret_type** (*str | unicode*) – Cannot be updated.

- **token_scopes** (*list[str]*) – List of OAuth scopes to assign to access_token secrets generated under this role set (access_token role sets only)
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_roleset (*name, mount_point='gcp'*)

Delete an existing roleset by the given name.

Supported methods: DELETE: /{mount_point}/roleset/{name} Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

generate_oauth2_access_token (*roleset, mount_point='gcp'*)

Generate an OAuth2 token with the scopes defined on the roleset.

This OAuth access token can be used in GCP API calls, e.g. curl -H “Authorization: Bearer \$TOKEN” ...

Supported methods: GET: /{mount_point}/token/{roleset}. Produces: 200 application/json

Parameters

- **roleset** (*str | unicode*) – Name of an roleset with secret type access_token to generate access_token under.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

generate_service_account_key (*roleset, key_algorithm='KEY_ALG_RSA_2048', key_type='TYPE_GOOGLE_CREDENTIALS_FILE', method='POST', mount_point='gcp'*)

Generate Secret (IAM Service Account Creds): Service Account Key

If using GET (‘read’), the optional parameters will be set to their defaults. Use POST if you want to specify different values for these params.

Parameters

- **roleset** (*str | unicode*) – Name of an roleset with secret type service_account_key to generate key under.
- **key_algorithm** (*str | unicode*) – Key algorithm used to generate key. Defaults to 2k RSA key You probably should not choose other values (i.e. 1k),
- **key_type** (*str | unicode*) – Private key type to generate. Defaults to JSON credentials file.
- **method** (*str | unicode*) – Supported methods: POST: /{mount_point}/key/{roleset}. Produces: 200 application/json GET: /{mount_point}/key/{roleset}. Produces: 200 application/json

- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_rolesets (*mount_point='gcp'*)

List configured rolesets.

Supported methods: LIST: */{mount_point}/rolesets*. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_config (*mount_point='gcp'*)

Read the configured shared information for the Gcp secrets engine.

Credentials will be omitted from returned data.

Supported methods: GET: */{mount_point}/config*. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_roleset (*name, mount_point='gcp'*)

Read a roleset.

Supported methods: GET: */{mount_point}/roleset/{name}*. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

rotate_roleset_account (*name, mount_point='gcp'*)

Rotate the service account this roleset uses to generate secrets.

This also replaces the key `access_token` roleset. This can be used to invalidate old secrets generated by the roleset or fix issues if a roleset’s service account (and/or keys) was changed outside of Vault (i.e. through GCP APIs/cloud console).

Supported methods: POST: */{mount_point}/roleset/{name}/rotate*. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the role.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

rotate_roleset_account_key (*name*, *mount_point='gcp'*)

Rotate the service account key this roleset uses to generate access tokens.

This does not recreate the roleset service account.

Supported methods: POST: `/{{mount_point}}/roleset/{{name}}/rotate-key`. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Name of the role.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

class hvac.api.secrets_engines.ActiveDirectory (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

Active Directory Secrets Engine (API). Reference: <https://www.vaultproject.io/api/secret/ad/index.html>

configure (*binddn=None*, *bindpass=None*, *url=None*, *userdn=None*, *upndomain=None*, *ttl=None*, *max_ttl=None*, *mount_point='ad'*, **args*, ***kwargs*)

Configure shared information for the ad secrets engine.

Supported methods: POST: `/{{mount_point}}/config`. Produces: 204 (empty body)

Parameters

- **binddn** (*str* | *unicode*) – Distinguished name of object to bind when performing user and group search.
- **bindpass** (*str* | *unicode*) – Password to use along with binddn when performing user search.
- **url** (*str* | *unicode*) – Base DN under which to perform user search.
- **userdn** (*str* | *unicode*) – Base DN under which to perform user search.
- **upndomain** (*str* | *unicode*) – userPrincipalDomain used to construct the UPN string for the authenticating user.
- **ttl** (*int* | *str*) – The default password time-to-live in seconds. Once the ttl has passed, a password will be rotated the next time it’s requested.
- **max_ttl** (*int* | *str*) – The maximum password time-to-live in seconds. No role will be allowed to set a custom ttl greater than the max_ttl integer number of seconds or Go duration format string.**
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

create_or_update_role (*name*, *service_account_name=None*, *ttl=None*, *mount_point='ad'*)

This endpoint creates or updates the ad role definition.

Parameters

- **name** (*str* | *unicode*) – Specifies the name of an existing role against which to create this ad credential.

- **service_account_name** (*str | unicode*) – The name of a pre-existing service account in Active Directory that maps to this role. This value is required on create and optional on update.
- **ttl** (*str | unicode*) – Specifies the TTL for this role. This is provided as a string duration with a time suffix like “30s” or “1h” or as seconds. If not provided, the default Vault TTL is used.
- **mount_point** (*str | unicode*) – Specifies the place where the secrets engine will be accessible (default: ad).

Returns The response of the request.

Return type requests.Response

delete_role (*name, mount_point='ad'*)

This endpoint deletes a ad role with the given name. Even if the role does not exist, this endpoint will still return a successful response. :param name: Specifies the name of the role to delete. :type name: str | unicode :param mount_point: Specifies the place where the secrets engine will be accessible (default: ad). :type mount_point: str | unicode :return: The response of the request. :rtype: requests.Response

list_roles (*mount_point='ad'*)

This endpoint lists all existing roles in the secrets engine. :return: The response of the request. :rtype: requests.Response

read_config (*mount_point='ad'*)

Read the configured shared information for the ad secrets engine.

Credentials will be omitted from returned data.

Supported methods: GET: /{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_role (*name, mount_point='ad'*)

This endpoint queries for information about a ad role with the given name. If no role exists with that name, a 404 is returned. :param name: Specifies the name of the role to query. :type name: str | unicode :param mount_point: Specifies the place where the secrets engine will be accessible (default: ad). :type mount_point: str | unicode :return: The response of the request. :rtype: requests.Response

class hvac.api.secrets_engines.**Identity** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

Identity Secrets Engine (API).

Reference: <https://www.vaultproject.io/api/secret/identity/entity.html>

create_or_update_entity (*name, entity_id=None, metadata=None, policies=None, disabled=None, mount_point='identity'*)

Create or update an Entity.

Supported methods: POST: /{mount_point}/entity. Produces: 200 application/json

Parameters

- **entity_id** (*str | unicode*) – ID of the entity. If set, updates the corresponding existing entity.

- **name** (*str | unicode*) – Name of the entity.
- **metadata** (*dict*) – Metadata to be associated with the entity.
- **policies** (*str | unicode*) – Policies to be tied to the entity.
- **disabled** (*bool*) – Whether the entity is disabled. Disabled entities’ associated tokens cannot be used, but are not revoked.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response for creates, the generic response object for updates, of the request.

Return type `dict | requests.Response`

create_or_update_entity_alias (*name, canonical_id, mount_accessor, alias_id=None, mount_point='identity'*)

Create a new alias for an entity.

Supported methods: POST: `/mount_point/entity-alias`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the alias. Name should be the identifier of the client in the authentication source. For example, if the alias belongs to userpass backend, the name should be a valid username within userpass backend. If alias belongs to GitHub, it should be the GitHub username.
- **alias_id** (*str | unicode*) – ID of the entity alias. If set, updates the corresponding entity alias.
- **canonical_id** (*str | unicode*) – Entity ID to which this alias belongs to.
- **mount_accessor** (*str | unicode*) – Accessor of the mount to which the alias should belong to.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `requests.Response`

create_or_update_entity_by_name (*name, metadata=None, policies=None, disabled=None, mount_point='identity'*)

Create or update an entity by a given name.

Supported methods: POST: `/mount_point/entity/name/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the entity.
- **metadata** (*dict*) – Metadata to be associated with the entity.
- **policies** (*str | unicode*) – Policies to be tied to the entity.
- **disabled** (*bool*) – Whether the entity is disabled. Disabled entities’ associated tokens cannot be used, but are not revoked.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response for creates, the generic response of the request for updates.

Return type `requests.Response | dict`

create_or_update_group (*name*, *group_id=None*, *group_type='internal'*, *metadata=None*, *policies=None*, *member_group_ids=None*, *member_entity_ids=None*, *mount_point='identity'*)

Create or update a Group.

Supported methods: POST: `/{mount_point}/group`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the group.
- **group_id** (*str | unicode*) – ID of the group. If set, updates the corresponding existing group.
- **group_type** (*str | unicode*) – Type of the group, internal or external. Defaults to internal.
- **metadata** (*dict*) – Metadata to be associated with the group.
- **policies** (*str | unicode*) – Policies to be tied to the group.
- **member_group_ids** (*str | unicode*) – Group IDs to be assigned as group members.
- **member_entity_ids** (*str | unicode*) – Entity IDs to be assigned as group members.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response where available, otherwise the generic response object, of the request.

Return type `dict | requests.Response`

create_or_update_group_alias (*name*, *alias_id=None*, *mount_accessor=None*, *canonical_id=None*, *mount_point='identity'*)

Creates or update a group alias.

Supported methods: POST: `/{mount_point}/group-alias`. Produces: 200 application/json

Parameters

- **alias_id** (*str | unicode*) – ID of the group alias. If set, updates the corresponding existing group alias.
- **name** (*str | unicode*) – Name of the group alias.
- **mount_accessor** (*str | unicode*) – Mount accessor to which this alias belongs to
- **canonical_id** (*str | unicode*) – ID of the group to which this is an alias.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `requests.Response`

create_or_update_group_by_name (*name*, *group_type=None*, *metadata=None*, *policies=None*, *member_group_ids=None*, *member_entity_ids=None*, *mount_point='identity'*)

Create or update a group by its name.

Supported methods: POST: `/{mount_point}/group/name/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the group.
- **group_type** (*str | unicode*) – Type of the group, internal or external. Defaults to internal.
- **metadata** (*dict*) – Metadata to be associated with the group.
- **policies** (*str | unicode*) – Policies to be tied to the group.
- **member_group_ids** (*str | unicode*) – Group IDs to be assigned as group members.
- **member_entity_ids** (*str | unicode*) – Entity IDs to be assigned as group members.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_entity (*entity_id, mount_point='identity'*)

Delete an entity and all its associated aliases.

Supported methods: DELETE: /{mount_point}/entity/id/{id}. Produces: 204 (empty body)

Parameters

- **entity_id** (*str*) – Identifier of the entity.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

delete_entity_alias (*alias_id, mount_point='identity'*)

Delete a entity alias.

Supported methods: DELETE: /{mount_point}/entity-alias/id/{alias_id}. Produces: 204 (empty body)

Parameters

- **alias_id** (*str | unicode*) – Identifier of the entity.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_entity_by_name (*name, mount_point='identity'*)

Delete an entity and all its associated aliases, given the entity name.

Supported methods: DELETE: /{mount_point}/entity/name/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Name of the entity.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_group (*group_id*, *mount_point*=*'identity'*)

Delete a group.

Supported methods: DELETE: /{mount_point}/group/id/{id}. Produces: 204 (empty body)

Parameters

- **group_id** (*str* | *unicode*) – Identifier of the entity.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_group_alias (*entity_id*, *mount_point*=*'identity'*)

Delete a group alias.

Supported methods: DELETE: /{mount_point}/group-alias/id/{id}. Produces: 204 (empty body)

Parameters

- **entity_id** (*str* | *unicode*) – ID of the group alias.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_group_by_name (*name*, *mount_point*=*'identity'*)

Delete a group, given its name.

Supported methods: DELETE: /{mount_point}/group/name/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Name of the group.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

list_entities (*method*=*'LIST'*, *mount_point*=*'identity'*)

List available entities entities by their identifiers.

Parameters

- **method** (*str* | *unicode*) – Supported methods: LIST: /{mount_point}/entity/id. Produces: 200 application/json GET: /{mount_point}/entity/id?list=true. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_entities_by_name (*method*=*'LIST'*, *mount_point*=*'identity'*)

List available entities by their names.

Parameters

- **method** (*str* | *unicode*) – Supported methods: LIST: `/{{mount_point}}/entity/name`. Produces: 200 application/json GET: `/{{mount_point}}/entity/name?list=true`. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_entity_aliases (*method*='LIST', *mount_point*='identity')

List available entity aliases by their identifiers.

Parameters

- **method** (*str* | *unicode*) – Supported methods: LIST: `/{{mount_point}}/entity-alias/id`. Produces: 200 application/json GET: `/{{mount_point}}/entity-alias/id?list=true`. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The the JSON response of the request.

Return type dict

list_group_aliases (*method*='LIST', *mount_point*='identity')

List available group aliases by their identifiers.

Parameters

- **method** (*str* | *unicode*) – Supported methods: LIST: `/{{mount_point}}/group-alias/id`. Produces: 200 application/json GET: `/{{mount_point}}/group-alias/id?list=true`. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The “data” key from the JSON response of the request.

Return type dict

list_groups (*method*='LIST', *mount_point*='identity')

List available groups by their identifiers.

Parameters

- **method** (*str* | *unicode*) – Supported methods: LIST: `/{{mount_point}}/group/id`. Produces: 200 application/json GET: `/{{mount_point}}/group/id?list=true`. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_groups_by_name (*method*='LIST', *mount_point*='identity')

List available groups by their names.

Parameters

- **method** (*str* | *unicode*) – Supported methods: LIST: `/{{mount_point}}/group/name`. Produces: 200 application/json GET: `/{{mount_point}}/group/name?list=true`. Produces: 200 application/json
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

lookup_entity (*name=None, entity_id=None, alias_id=None, alias_name=None, alias_mount_accessor=None, mount_point='identity'*)

Query an entity based on the given criteria.

The criteria can be name, id, alias_id, or a combination of alias_name and alias_mount_accessor.

Supported methods: POST: /{mount_point}/lookup/entity. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the entity.
- **entity_id** (*str | unicode*) – ID of the entity.
- **alias_id** (*str | unicode*) – ID of the alias.
- **alias_name** (*str | unicode*) – Name of the alias. This should be supplied in conjunction with alias_mount_accessor.
- **alias_mount_accessor** (*str | unicode*) – Accessor of the mount to which the alias belongs to. This should be supplied in conjunction with alias_name.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request if a entity / entity alias is found in the lookup, None otherwise.

Return type dict | None

lookup_group (*name=None, group_id=None, alias_id=None, alias_name=None, alias_mount_accessor=None, mount_point='identity'*)

Query a group based on the given criteria.

The criteria can be name, id, alias_id, or a combination of alias_name and alias_mount_accessor.

Supported methods: POST: /{mount_point}/lookup/group. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the group.
- **group_id** (*str | unicode*) – ID of the group.
- **alias_id** (*str | unicode*) – ID of the alias.
- **alias_name** (*str | unicode*) – Name of the alias. This should be supplied in conjunction with alias_mount_accessor.
- **alias_mount_accessor** (*str | unicode*) – Accessor of the mount to which the alias belongs to. This should be supplied in conjunction with alias_name.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request if a group / group alias is found in the lookup, None otherwise.

Return type dict | None

merge_entities (*from_entity_ids, to_entity_id, force=None, mount_point='identity'*)

Merge many entities into one entity.

Supported methods: POST: /{mount_point}/entity/merge. Produces: 204 (empty body)

Parameters

- **from_entity_ids** (*array*) – Entity IDs which needs to get merged.
- **to_entity_id** (*str | unicode*) – Entity ID into which all the other entities need to get merged.
- **force** (*bool*) – Setting this will follow the ‘mine’ strategy for merging MFA secrets. If there are secrets of the same type both in entities that are merged from and in entity into which all others are getting merged, secrets in the destination will be unaltered. If not set, this API will throw an error containing all the conflicts.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

read_entity (*entity_id, mount_point='identity'*)

Query an entity by its identifier.

Supported methods: GET: /auth/{mount_point}/entity/id/{id}. Produces: 200 application/json

Parameters

- **entity_id** (*str*) – Identifier of the entity.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the request.

Return type dict

read_entity_alias (*alias_id, mount_point='identity'*)

Query the entity alias by its identifier.

Supported methods: GET: /{mount_point}/entity-alias/id/{id}. Produces: 200 application/json

Parameters

- **alias_id** (*str | unicode*) – Identifier of entity alias.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_entity_by_name (*name, mount_point='identity'*)

Query an entity by its name.

Supported methods: GET: /{mount_point}/entity/name/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the entity.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

read_group (*group_id*, *mount_point='identity'*)

Query the group by its identifier.

Supported methods: GET: `/{{mount_point}}/group/id/{{id}}`. Produces: 200 application/json

Parameters

- **group_id** (*str | unicode*) – Identifier of the group.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

read_group_alias (*alias_id*, *mount_point='identity'*)

Query the group alias by its identifier.

Supported methods: GET: `/{{mount_point}}/group-alias/id/:id`. Produces: 200 application/json

Parameters

- **alias_id** (*str | unicode*) – ID of the group alias.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_group_by_name (*name*, *mount_point='identity'*)

Query a group by its name.

Supported methods: GET: `/{{mount_point}}/group/name/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the group.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

update_entity (*entity_id*, *name=None*, *metadata=None*, *policies=None*, *disabled=None*,
mount_point='identity')

Update an existing entity.

Supported methods: POST: `/{{mount_point}}/entity/id/{{id}}`. Produces: 200 application/json

Parameters

- **entity_id** (*str | unicode*) – Identifier of the entity.
- **name** (*str | unicode*) – Name of the entity.
- **metadata** (*dict*) – Metadata to be associated with the entity.
- **policies** (*str | unicode*) – Policies to be tied to the entity.
- **disabled** (*bool*) – Whether the entity is disabled. Disabled entities’ associated tokens cannot be used, but are not revoked.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response where available, otherwise the generic response object, of the request.

Return type dict | requests.Response

update_entity_alias (*alias_id, name, canonical_id, mount_accessor, mount_point='identity'*)

Update an existing entity alias.

Supported methods: POST: /{mount_point}/entity-alias/id/{id}. Produces: 200 application/json

Parameters

- **alias_id** (*str | unicode*) – Identifier of the entity alias.
- **name** (*str | unicode*) – Name of the alias. Name should be the identifier of the client in the authentication source. For example, if the alias belongs to userpass backend, the name should be a valid username within userpass backend. If alias belongs to GitHub, it should be the GitHub username.
- **canonical_id** (*str | unicode*) – Entity ID to which this alias belongs to.
- **mount_accessor** (*str | unicode*) – Accessor of the mount to which the alias should belong to.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response where available, otherwise the generic response object, of the request.

Return type dict | requests.Response

update_group (*group_id, name, group_type=None, metadata=None, policies=None, member_group_ids=None, member_entity_ids=None, mount_point='identity'*)

Update an existing group.

Supported methods: POST: /{mount_point}/group/id/{id}. Produces: 200 application/json

Parameters

- **group_id** (*str | unicode*) – Identifier of the entity.
- **name** (*str | unicode*) – Name of the group.
- **group_type** (*str | unicode*) – Type of the group, internal or external. Defaults to internal.
- **metadata** (*dict*) – Metadata to be associated with the group.
- **policies** (*str | unicode*) – Policies to be tied to the group.
- **member_group_ids** (*str | unicode*) – Group IDs to be assigned as group members.
- **member_entity_ids** (*str | unicode*) – Entity IDs to be assigned as group members.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response where available, otherwise the generic response object, of the request.

Return type dict | requests.Response

update_group_alias (*entity_id*, *name*, *mount_accessor=None*, *canonical_id=None*, *mount_point='identity'*)

Update an existing group alias.

Supported methods: POST: `/{mount_point}/group-alias/id/{id}`. Produces: 200 application/json

Parameters

- **entity_id** (*str | unicode*) – ID of the group alias.
- **name** (*str | unicode*) – Name of the group alias.
- **mount_accessor** (*str | unicode*) – Mount accessor to which this alias belongs to
- **canonical_id** (*str | unicode*) – ID of the group to which this is an alias.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

static validate_member_id_params_for_group_type (*group_type*, *params*, *member_group_ids*, *member_entity_ids*)

Determine whether member ID parameters can be sent with a group create / update request.

These parameters are only allowed for the internal group type. If they’re set for an external group type, Vault returns a “error” response.

Parameters

- **group_type** (*str | unicode*) – Type of the group, internal or external
- **params** (*dict*) – Params dict to conditionally add the member entity/group ID’s to.
- **member_group_ids** (*str | unicode*) – Group IDs to be assigned as group members.
- **member_entity_ids** (*str | unicode*) – Entity IDs to be assigned as group members.

Returns Params dict with conditionally added member entity/group ID’s.

Return type dict

class hvac.api.secrets_engines.**Kv** (*adapter*, *default_kv_version='2'*)

Bases: hvac.api.vault_api_base.VaultApiBase

Class containing methods for the key/value secrets_engines backend API routes. Reference: <https://www.vaultproject.io/docs/secrets/kv/index.html>

__init__ (*adapter*, *default_kv_version='2'*)

Create a new Kv instance.

Parameters

- **adapter** (*hvac.adapters.Adapter*) – Instance of *hvac.adapters.Adapter*; used for performing HTTP requests.
- **default_kv_version** (*str | unicode*) – KV version number (e.g., ‘1’) to use as the default when accessing attributes/methods under this class.

allowed_kv_versions = ['1', '2']

default_kv_version**v1**

Accessor for kv version 1 class / method. Provided via the `hvac.api.secrets_engines.kv_v1.KvV1` class.

Returns This Kv instance's associated KvV1 instance.

Return type `hvac.api.secrets_engines.kv_v1.KvV1`

v2

Accessor for kv version 2 class / method. Provided via the `hvac.api.secrets_engines.kv_v2.KvV2` class.

Returns This Kv instance's associated KvV2 instance.

Return type `hvac.api.secrets_engines.kv_v2.KvV2`

class `hvac.api.secrets_engines.KvV1` (*adapter*)

Bases: `hvac.api.vault_api_base.VaultApiBase`

KV Secrets Engine - Version 1 (API).

Reference: <https://www.vaultproject.io/api/secrets/kv/kv-v1.html>

create_or_update_secret (*path, secret, method=None, mount_point='secret'*)

Store a secret at the specified location.

If the value does not yet exist, the calling token must have an ACL policy granting the create capability. If the value already exists, the calling token must have an ACL policy granting the update capability.

Supported methods: POST: `/{mount_point}/{path}`. Produces: 204 (empty body) PUT: `/{mount_point}/{path}`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path of the secrets to create/update. This is specified as part of the URL.
- **secret** (*dict*) – Specifies keys, paired with associated values, to be held at the given location. Multiple key/value pairs can be specified, and all will be returned on a read operation. A key called `ttl` will trigger some special behavior. See the Vault KV secrets engine documentation for details.
- **method** (*str | unicode*) – Optional parameter to explicitly request a POST (create) or PUT (update) request to the selected kv secret engine. If no argument is provided for this parameter, hvac attempts to intelligently determine which method is appropriate.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the `create_or_update_secret` request.

Return type `requests.Response`

delete_secret (*path, mount_point='secret'*)

Delete the secret at the specified location.

Supported methods: DELETE: `/{mount_point}/{path}`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to delete. This is specified as part of the URL.

- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the delete_secret request.

Return type requests.Response

list_secrets (*path, mount_point='secret'*)

Return a list of key names at the specified location.

Folders are suffixed with /. The input must be a folder; list on a file will not return a value. Note that no policy-based filtering is performed on keys; do not encode sensitive information in key names. The values themselves are not accessible via this command.

Supported methods: LIST: `/{{mount_point}}/{{path}}`. Produces: 200 application/json

Parameters

- **path** (*str | unicode*) – Specifies the path of the secrets to list. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the list_secrets request.

Return type dict

read_secret (*path, mount_point='secret'*)

Retrieve the secret at the specified location.

Supported methods: GET: `/{{mount_point}}/{{path}}`. Produces: 200 application/json

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to read. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the read_secret request.

Return type dict

class hvac.api.secrets_engines.**KvV2** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

KV Secrets Engine - Version 2 (API).

Reference: <https://www.vaultproject.io/api/secret/kv/kv-v2.html>

configure (*max_versions=10, cas_required=None, mount_point='secret'*)

Configure backend level settings that are applied to every key in the key-value store.

Supported methods: POST: `/{{mount_point}}/config`. Produces: 204 (empty body)

Parameters

- **max_versions** (*int*) – The number of versions to keep per key. This value applies to all keys, but a key’s metadata setting can overwrite this value. Once a key has more than the configured allowed versions the oldest version will be permanently deleted. Defaults to 10.
- **cas_required** (*bool*) – If true all keys will require the cas parameter to be set on all write requests.

- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

create_or_update_secret (*path, secret, cas=None, mount_point='secret'*)

Create a new version of a secret at the specified location.

If the value does not yet exist, the calling token must have an ACL policy granting the create capability. If the value already exists, the calling token must have an ACL policy granting the update capability.

Supported methods: POST: `/mount_point/data/path`. Produces: 200 application/json

Parameters

- **path** (*str | unicode*) – Path
- **cas** (*int*) – Set the “cas” value to use a Check-And-Set operation. If not set the write will be allowed. If set to 0 a write will only be allowed if the key doesn’t exist. If the index is non-zero the write will only be allowed if the key’s current version matches the version specified in the cas parameter.
- **secret** (*dict*) – The contents of the “secret” dict will be stored and returned on read.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the request.

Return type dict

delete_latest_version_of_secret (*path, mount_point='secret'*)

Issue a soft delete of the secret’s latest version at the specified location.

This marks the version as deleted and will stop it from being returned from reads, but the underlying data will not be removed. A delete can be undone using the undelete path.

Supported methods: DELETE: `/mount_point/data/path`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to delete. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

delete_metadata_and_all_versions (*path, mount_point='secret'*)

Delete (permanently) the key metadata and all version data for the specified key.

All version history will be removed.

Supported methods: DELETE: `/mount_point/metadata/path`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to delete. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

delete_secret_versions (*path*, *versions*, *mount_point*='secret')

Issue a soft delete of the specified versions of the secret.

This marks the versions as deleted and will stop them from being returned from reads, but the underlying data will not be removed. A delete can be undone using the undelete path.

Supported methods: POST: /{mount_point}/delete/{path}. Produces: 204 (empty body)

Parameters

- **path** (*str* | *unicode*) – Specifies the path of the secret to delete. This is specified as part of the URL.
- **versions** (*int*) – The versions to be deleted. The versioned data will not be deleted, but it will no longer be returned in normal get requests.
- **mount_point** (*str* | *unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

destroy_secret_versions (*path*, *versions*, *mount_point*='secret')

Permanently remove the specified version data and numbers for the provided path from the key-value store.

Supported methods: POST: /{mount_point}/destroy/{path}. Produces: 204 (empty body)

Parameters

- **path** (*str* | *unicode*) – Specifies the path of the secret to destroy. This is specified as part of the URL.
- **versions** (*list of int*) – The versions to destroy. Their data will be permanently deleted.
- **mount_point** (*str* | *unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

list_secrets (*path*, *mount_point*='secret')

Return a list of key names at the specified location.

Folders are suffixed with /. The input must be a folder; list on a file will not return a value. Note that no policy-based filtering is performed on keys; do not encode sensitive information in key names. The values themselves are not accessible via this command.

Supported methods: LIST: /{mount_point}/metadata/{path}. Produces: 200 application/json

Parameters

- **path** (*str* | *unicode*) – Specifies the path of the secrets to list. This is specified as part of the URL.
- **mount_point** (*str* | *unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the request.

Return type dict

patch (*path, secret, mount_point='secret'*)

Set or update data in the KV store without overwriting.

Parameters

- **path** (*str | unicode*) – Path
- **secret** (*dict*) – The contents of the “secret” dict will be stored and returned on read.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the create_or_update_secret request.

Return type dict

read_configuration (*mount_point='secret'*)

Read the KV Version 2 configuration.

Supported methods: GET: /auth/{mount_point}/config. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the request.

Return type dict

read_secret_metadata (*path, mount_point='secret'*)

Retrieve the metadata and versions for the secret at the specified path.

Supported methods: GET: /{mount_point}/metadata/{path}. Produces: 200 application/json

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to read. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the request.

Return type dict

read_secret_version (*path, version=None, mount_point='secret'*)

Retrieve the secret at the specified location.

Supported methods: GET: /{mount_point}/data/{path}. Produces: 200 application/json

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to read. This is specified as part of the URL.
- **version** (*int*) – Specifies the version to return. If not set the latest version is returned.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The JSON response of the request.

Return type dict

undelese_secret_versions (*path, versions, mount_point='secret'*)

Undelete the data for the provided version and path in the key-value store.

This restores the data, allowing it to be returned on get requests.

Supported methods: POST: `/mount_point/undelete/path`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path of the secret to undelete. This is specified as part of the URL.
- **versions** (*list of int*) – The versions to undelete. The versions will be restored and their data will be returned on normal get requests.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

update_metadata (*path, max_versions=None, cas_required=None, mount_point='secret'*)
 Updates the max_versions of cas_required setting on an existing path.

Supported methods: POST: `/mount_point/metadata/path`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Path
- **max_versions** (*int*) – The number of versions to keep per key. If not set, the backend’s configured max version is used. Once a key has more than the configured allowed versions the oldest version will be permanently deleted.
- **cas_required** (*bool*) – If true the key will require the cas parameter to be set on all write requests. If false, the backend’s configuration will be used.
- **mount_point** (*str | unicode*) – The “path” the secret engine was mounted on.

Returns The response of the request.

Return type requests.Response

class hvac.api.secrets_engines.**Pki** (*adapter*)
 Bases: hvac.api.vault_api_base.VaultApiBase
 Pki Secrets Engine (API).

Reference: <https://www.vaultproject.io/api/secret/pki/index.html>

create_or_update_role (*name, extra_params={}, mount_point='pki'*)
 Create/Update Role.

Creates or updates the role definition.

Supported methods: POST: `/mount_point/roles/name`. Produces: 200 application/json

Parameters

- **name** – The name of the role to create.
- **extra_params** – A dictionary with extra parameters.
- **mount_point** – The “path” the method/backend was mounted on.

Name name str | unicode

Name extra_params dict

Name mount_point str | unicode

Returns The JSON response of the request.

Rname requests.Response

delete_role (*name*, *mount_point*='pki')

Delete Role.

Deletes the role definition.

Supported methods: DELETE: /{mount_point}/roles/{name}. Produces: 200 application/json

Parameters

- **name** – The name of the role to delete.
- **mount_point** – The “path” the method/backend was mounted on.

Name name str | unicode

Name mount_point str | unicode

Returns The JSON response of the request.

Return type requests.Response

delete_root (*mount_point*='pki')

Delete Root.

Deletes the current CA key.

Supported methods: DELETE: /{mount_point}/root. Produces: 200 application/json

Parameters mount_point (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

generate_certificate (*name*, *common_name*, *extra_params*={}, *mount_point*='pki')

Generate Certificate.

Generates a new set of credentials (private key and certificate) based on the role named in the endpoint.

Supported methods: POST: /{mount_point}/issue/{name}. Produces: 200 application/json

Parameters

- **name** – The name of the role to create the certificate against.
- **common_name** – The requested CN for the certificate.
- **extra_params** – A dictionary with extra parameters.
- **mount_point** – The “path” the method/backend was mounted on.

Name name str | unicode

Name common_name str | unicode

Name extra_params dict

Name mount_point str | unicode

Returns The JSON response of the request.

Return type requests.Response

generate_intermediate (*type*, *common_name*, *extra_params*={}, *mount_point*='pki')

Generate Intermediate.

Generates a new private key and a CSR for signing.

Supported methods: POST: /{mount_point}/intermediate/generate/{type}. Produces: 200 application/json

Parameters

- **type** (*str* | *unicode*) – Specifies the type to create. *exported* (private key also exported) or *internal*.
- **common_name** (*str* | *unicode*) – Specifies the requested CN for the certificate.
- **extra_params** (*dict*) – Dictionary with extra parameters.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

generate_root (*type*, *common_name*, *extra_params*={}, *mount_point*='pki')

Generate Root.

Generates a new self-signed CA certificate and private key.

Supported methods: POST: /{mount_point}/root/generate/{type}. Produces: 200 application/json

Parameters

- **type** (*str* | *unicode*) – Specifies the type to create. *exported* (private key also exported) or *internal*.
- **common_name** (*str* | *unicode*) – The requested CN for the certificate.
- **extra_params** (*dict*) – A dictionary with extra parameters.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

list_certificates (*mount_point*='pki')

List Certificates.

The list of the current certificates by serial number only.

Supported methods: LIST: /{mount_point}/certs. Produces: 200 application/json

Parameters **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

list_roles (*mount_point='pki'*)

List Roles.

Get a list of available roles.

Supported methods: LIST: `/{{mount_point}}/roles`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_ca_certificate (*mount_point='pki'*)

Read CA Certificate.

Retrieves the CA certificate in raw DER-encoded form.

Supported methods: GET: `/{{mount_point}}/ca/pem`. Produces: String

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The certificate as pem.

Return type str

read_ca_certificate_chain (*mount_point='pki'*)

Read CA Certificate Chain.

Retrieves the CA certificate chain, including the CA in PEM format.

Supported methods: GET: `/{{mount_point}}/ca_chain`. Produces: String

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The certificate chain as pem.

Return type str

read_certificate (*serial, mount_point='pki'*)

Read Certificate.

Retrieves one of a selection of certificates.

Supported methods: GET: `/{{mount_point}}/cert/{{serial}}`. Produces: 200 application/json

Parameters

- **serial** (*str | unicode*) – the serial of the key to read.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_crl (*mount_point='pki'*)

Read CRL.

Retrieves the current CRL in PEM format. This endpoint is unauthenticated.

Supported methods: GET: `/{{mount_point}}/crl/pem`. Produces: 200 application/pkix-crl

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The content of the request e.g. CRL string representation.

Return type str

read_crl_configuration (*mount_point='pki'*)

Read CRL Configuration.

Getting the duration for which the generated CRL should be marked valid.

Supported methods: GET: `/{{mount_point}}/config/crl`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_role (*name, mount_point='pki'*)

Read Role.

Queries the role definition.

Supported methods: GET: `/{{mount_point}}/roles/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – The name of the role to read.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

read_urls (*mount_point='pki'*)

Read URLs.

Fetches the URLs to be encoded in generated certificates.

Supported methods: GET: `/{{mount_point}}/config/urls`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

revoke_certificate (*serial_number, mount_point='pki'*)

Revoke Certificate.

Revokes a certificate using its serial number.

Supported methods: POST: `/{{mount_point}}/revoke`. Produces: 200 application/json

Parameters

- **serial_number** – The serial number of the certificate to revoke.
- **mount_point** – The “path” the method/backend was mounted on.

Name serial_number str | unicode

Name mount_point str | unicode

Returns The JSON response of the request.

Return type requests.Response

rotate_crl (*mount_point='pki'*)

Rotate CRLs.

Forces a rotation of the CRL.

Supported methods: GET: /{mount_point}/crl/rotate. Produces: 200 application/json

Parameters mount_point (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type dict

set_crl_configuration (*expiry=None, disable=None, extra_params={}, mount_point='pki'*)

Set CRL Configuration.

Setting the duration for which the generated CRL should be marked valid. If the CRL is disabled, it will return a signed but zero-length CRL for any request. If enabled, it will re-build the CRL.

Supported methods: POST: /{mount_point}/config/crl. Produces: 200 application/json

Parameters mount_point (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

set_signed_intermediate (*certificate, mount_point='pki'*)

Set Signed Intermediate.

Allows submitting the signed CA certificate corresponding to a private key generated via “Generate Intermediate”

Supported methods: POST: /{mount_point}/intermediate/set-signed. Produces: 200 application/json

Parameters

- **certificate** (*str | unicode*) – Specifies the certificate in PEM format.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

set_urls (*params, mount_point='pki'*)

Set URLs.

Setting the issuing certificate endpoints, CRL distribution points, and OCSP server endpoints that will be encoded into issued certificates. You can update any of the values at any time without affecting the other existing values. To remove the values, simply use a blank string as the parameter.

Supported methods: POST: `/mount_point/config/urls`. Produces: 200 application/json

Parameters `mount_point` (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

sign_certificate (*name, csr, common_name, extra_params={}, mount_point='pki'*)

Sign Certificate.

Signs a new certificate based upon the provided CSR and the supplied parameters.

Supported methods: POST: `/mount_point/sign/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – The role to sign the certificate.
- **csr** (*str | unicode*) – The PEM-encoded CSR.
- **common_name** (*str | unicode*) – The requested CN for the certificate. If the CN is allowed by role policy, it will be issued.
- **extra_params** (*dict*) – A dictionary with extra parameters.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

sign_intermediate (*csr, common_name, extra_params={}, mount_point='pki'*)

Sign Intermediate.

Issue a certificate with appropriate values for acting as an intermediate CA.

Supported methods: POST: `/mount_point/root/sign-intermediate`. Produces: 200 application/json

Parameters

- **csr** (*str | unicode*) – The PEM-encoded CSR.
- **common_name** (*str | unicode*) – The requested CN for the certificate.
- **extra_params** (*dict*) – Dictionary with extra parameters.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

sign_self_issued (*certificate, mount_point='pki'*)

Sign Self-Issued.

Sign a self-issued certificate.

Supported methods: POST: `/mount_point/root/sign-self-issued`. Produces: 200 application/json

Parameters

- **certificate** (*str* | *unicode*) – The PEM-encoded self-issued certificate.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

sign_verbatim (*csr*, *name=False*, *extra_params={}*, *mount_point='pki'*)

Sign Verbatim.

Signs a new certificate based upon the provided CSR.

Supported methods: POST: /{mount_point}/sign-verbatim. Produces: 200 application/json

Parameters

- **csr** (*str* | *unicode*) – The PEM-encoded CSR.
- **name** (*str* | *unicode*) – Specifies a role.
- **extra_params** (*dict*) – A dictionary with extra parameters.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

submit_ca_information (*pem_bundle*, *mount_point='pki'*)

Submit CA Information.

Submitting the CA information for the backend.

Supported methods: POST: /{mount_point}/config/ca. Produces: 200 application/json

Parameters **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

tidy (*extra_params={}*, *mount_point='pki'*)

Tidy.

Allows tidying up the storage backend and/or CRL by removing certificates that have expired and are past a certain buffer period beyond their expiration time.

Supported methods: POST: /{mount_point}/tidy. Produces: 200 application/json

Parameters

- **extra_params** (*dict*) – A dictionary with extra parameters.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

class hvac.api.secrets_engines.**Transit** (*adapter*)
 Bases: hvac.api.vault_api_base.VaultApiBase

Transit Secrets Engine (API).

Reference: <https://www.vaultproject.io/api/secret/transit/index.html>

backup_key (*name*, *mount_point='transit'*)
 Return a plaintext backup of a named key.

The backup contains all the configuration data and keys of all the versions along with the HMAC key. The response from this endpoint can be used with the /restore endpoint to restore the key.

Supported methods: GET: /{mount_point}/backup/{name}. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Name of the key.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

create_key (*name*, *convergent_encryption=None*, *derived=None*, *exportable=None*, *allow_plaintext_backup=None*, *key_type=None*, *mount_point='transit'*)
 Create a new named encryption key of the specified type.

The values set here cannot be changed after key creation.

Supported methods: POST: /{mount_point}/keys/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to create. This is specified as part of the URL.
- **convergent_encryption** (*bool*) – If enabled, the key will support convergent encryption, where the same plaintext creates the same ciphertext. This requires derived to be set to true. When enabled, each encryption(/decryption/rewrap/datakey) operation will derive a nonce value rather than randomly generate it.
- **derived** (*bool*) – Specifies if key derivation is to be used. If enabled, all encrypt/decrypt requests to this named key must provide a context which is used for key derivation.
- **exportable** (*bool*) – Enables keys to be exportable. This allows for all the valid keys in the key ring to be exported. Once set, this cannot be disabled.
- **allow_plaintext_backup** (*bool*) – If set, enables taking backup of named key in the plaintext format. Once set, this cannot be disabled.
- **key_type** (*str | unicode*) – Specifies the type of key to create. The currently-supported types are:
 - **aes256-gcm96**: AES-256 wrapped with GCM using a 96-bit nonce size AEAD
 - **chacha20-poly1305**: ChaCha20-Poly1305 AEAD (symmetric, supports derivation and convergent encryption)
 - **ed25519**: ED25519 (asymmetric, supports derivation).
 - **ecdsa-p256**: ECDSA using the P-256 elliptic curve (asymmetric)

- **rsa-2048**: RSA with bit size of 2048 (asymmetric)
- **rsa-4096**: RSA with bit size of 4096 (asymmetric)
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

decrypt_data (*name, ciphertext, context=None, nonce=None, batch_input=None, mount_point='transit'*)

Decrypt the provided ciphertext using the named key.

Supported methods: POST: `/mount_point/decrypt/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to decrypt against. This is specified as part of the URL.
- **ciphertext** (*str | unicode*) – the ciphertext to decrypt.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.
- **nonce** (*str | unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters ‘ciphertext’, ‘context’ and ‘nonce’ are also set, they will be ignored. Format for the input goes like this: `[dict(context="b64_context", ciphertext="b64_plaintext"), ...]`
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

delete_key (*name, mount_point='transit'*)

Delete a named encryption key.

It will no longer be possible to decrypt any data encrypted with the named key. Because this is a potentially catastrophic operation, the `deletion_allowed` tunable must be set in the key’s `/config` endpoint.

Supported methods: DELETE: `/mount_point/keys/{name}`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to delete. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

encrypt_data (*name, plaintext, context=None, key_version=None, nonce=None, batch_input=None, type=None, convergent_encryption=None, mount_point='transit'*)

Encrypt the provided plaintext using the named key.

This path supports the create and update policy capabilities as follows: if the user has the create capability for this endpoint in their policies, and the key does not exist, it will be upserted with default values (whether the key requires derivation depends on whether the context parameter is empty or not). If the user only has update capability and the key does not exist, an error will be returned.

Supported methods: POST: `/{{mount_point}}/encrypt/{{name}}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to encrypt against. This is specified as part of the URL.
- **plaintext** (*str | unicode*) – Specifies base64 encoded plaintext to be encoded.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled for this key.
- **key_version** (*int*) – Specifies the version of the key to use for encryption. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **nonce** (*str | unicode*) – Specifies the base64 encoded nonce value. This must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+. The value must be exactly 96 bits (12 bytes) long and the user must ensure that for any given context (and thus, any given encryption key) this nonce value is never reused.
- **batch_input** (*List[dict]*) – Specifies a list of items to be encrypted in a single batch. When this parameter is set, if the parameters ‘plaintext’, ‘context’ and ‘nonce’ are also set, they will be ignored. The format for the input is: `[dict(context="b64_context", plaintext="b64_plaintext"), ...]`
- **type** (*str | unicode*) – This parameter is required when encryption key is expected to be created. When performing an upsert operation, the type of key to create.
- **convergent_encryption** (*str | unicode*) – This parameter will only be used when a key is expected to be created. Whether to support convergent encryption. This is only supported when using a key with key derivation enabled and will require all requests to carry both a context and 96-bit (12-byte) nonce. The given nonce will be used in place of a randomly generated nonce. As a result, when the same context and nonce are supplied, the same ciphertext is generated. It is very important when using this mode that you ensure that all nonces are unique for a given context. Failing to do so will severely impact the ciphertext’s security.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

export_key (*name, key_type, version=None, mount_point='transit'*)

Return the named key.

The keys object shows the value of the key for each version. If version is specified, the specific version will be returned. If latest is provided as the version, the current key will be provided. Depending on the type of key, different information may be returned. The key must be exportable to support this operation and the version must still be valid.

Supported methods: GET: `/{{mount_point}}/export/{{key_type}}/{{name}}/{{version}}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to read information about. This is specified as part of the URL.
- **key_type** (*str | unicode*) – Specifies the type of the key to export. This is specified as part of the URL. Valid values are: encryption-key signing-key hmac-key
- **version** (*str | unicode*) – Specifies the version of the key to read. If omitted, all versions of the key will be returned. If the version is set to latest, the current key will be returned.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

generate_data_key (*name, key_type, context=None, nonce=None, bits=None, mount_point='transit'*)

Generates a new high-entropy key and the value encrypted with the named key.

Optionally return the plaintext of the key as well. Whether plaintext is returned depends on the path; as a result, you can use Vault ACL policies to control whether a user is allowed to retrieve the plaintext value of a key. This is useful if you want an untrusted user or operation to generate keys that are then made available to trusted users.

Supported methods: POST: `/{mount_point}/datakey/{key_type}/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to use to encrypt the datakey. This is specified as part of the URL.
- **key_type** (*str | unicode*) – Specifies the type of key to generate. If plaintext, the plaintext key will be returned along with the ciphertext. If wrapped, only the ciphertext value will be returned. This is specified as part of the URL.
- **context** (*str | unicode*) – Specifies the key derivation context, provided as a base64-encoded string. This must be provided if derivation is enabled.
- **nonce** (*str | unicode*) – Specifies a nonce value, provided as base64 encoded. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+. The value must be exactly 96 bits (12 bytes) long and the user must ensure that for any given context (and thus, any given encryption key) this nonce value is never reused.
- **bits** (*int*) – Specifies the number of bits in the desired key. Can be 128, 256, or 512.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

generate_hmac (*name, hash_input, key_version=None, algorithm=None, mount_point='transit'*)

Return the digest of given data using the specified hash algorithm and the named key.

The key can be of any type supported by transit; the raw key will be marshaled into bytes to be used for the HMAC function. If the key is of a type that supports rotation, the latest (current) version will be used.

Supported methods: POST: `/{{mount_point}}/hmac/{{name}}/{{algorithm}}`. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to generate hmac against. This is specified as part of the URL.
- **hash_input** – Specifies the base64 encoded input data.
- **key_version** (*int*) – Specifies the version of the key to use for the operation. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **algorithm** (*str* | *unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

generate_random_bytes (*n_bytes=None*, *output_format=None*, *mount_point='transit'*)
Return high-quality random bytes of the specified length.

Supported methods: POST: `/{{mount_point}}/random/{{bytes}}`. Produces: 200 application/json

Parameters

- **n_bytes** (*int*) – Specifies the number of bytes to return. This value can be specified either in the request body, or as a part of the URL.
- **output_format** (*str* | *unicode*) – Specifies the output encoding. Valid options are hex or base64.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

hash_data (*hash_input*, *algorithm=None*, *output_format=None*, *mount_point='transit'*)
Return the cryptographic hash of given data using the specified algorithm.

Supported methods: POST: `/{{mount_point}}/hash/{{algorithm}}`. Produces: 200 application/json

Parameters

- **hash_input** (*str* | *unicode*) – Specifies the base64 encoded input data.
- **algorithm** (*str* | *unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **output_format** (*str* | *unicode*) – Specifies the output encoding. This can be either hex or base64.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

list_keys (*mount_point='transit'*)

List keys.

Only the key names are returned (not the actual keys themselves).

Supported methods: LIST: `/mount_point/keys`. Produces: 200 application/json

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

read_key (*name, mount_point='transit'*)

Read information about a named encryption key.

The keys object shows the creation time of each key version; the values are not the keys themselves. Depending on the type of key, different information may be returned, e.g. an asymmetric key will return its public key in a standard format for the type.

Supported methods: GET: `/mount_point/keys/{name}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to read. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the read_key request.

Return type requests.Response

restore_key (*backup, name=None, force=None, mount_point='transit'*)

Restore the backup as a named key.

This will restore the key configurations and all the versions of the named key along with HMAC keys. The input to this endpoint should be the output of /backup endpoint. For safety, by default the backend will refuse to restore to an existing key. If you want to reuse a key name, it is recommended you delete the key before restoring. It is a good idea to attempt restoring to a different key name first to verify that the operation successfully completes.

Supported methods: POST: `/mount_point/restore(/name)`. Produces: 204 (empty body)

Parameters

- **backup** (*str | unicode*) – Backed up key data to be restored. This should be the output from the /backup endpoint.
- **name** (*str | unicode*) – If set, this will be the name of the restored key.
- **force** (*bool*) – If set, force the restore to proceed even if a key by this name already exists.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

rewrap_data (*name, ciphertext, context=None, key_version=None, nonce=None, batch_input=None, mount_point='transit'*)

Rewrap the provided ciphertext using the latest version of the named key.

Because this never returns plaintext, it is possible to delegate this functionality to untrusted users or scripts.

Supported methods: POST: `/{{mount_point}}/rewrap/{{name}}`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to re-encrypt against. This is specified as part of the URL.
- **ciphertext** (*str | unicode*) – Specifies the ciphertext to re-encrypt.
- **context** (*str | unicode*) – Specifies the base64 encoded context for key derivation. This is required if key derivation is enabled.
- **key_version** (*int*) – Specifies the version of the key to use for the operation. If not set, uses the latest version. Must be greater than or equal to the key's `min_encryption_version`, if set.
- **nonce** (*str | unicode*) – Specifies a base64 encoded nonce value used during encryption. Must be provided if convergent encryption is enabled for this key and the key was generated with Vault 0.6.1. Not required for keys created in 0.6.2+.
- **batch_input** (*List[dict]*) – Specifies a list of items to be decrypted in a single batch. When this parameter is set, if the parameters 'ciphertext', 'context' and 'nonce' are also set, they will be ignored. Format for the input goes like this: `[dict(context="b64_context", ciphertext="b64_plaintext"), ...]`
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

rotate_key (*name, mount_point='transit'*)

Rotate the version of the named key.

After rotation, new plaintext requests will be encrypted with the new version of the key. To upgrade ciphertext to be encrypted with the latest version of the key, use the rewrap endpoint. This is only supported with keys that support encryption and decryption operations.

Supported methods: POST: `/{{mount_point}}/keys/{{name}}/rotate`. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to read information about. This is specified as part of the URL.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

sign_data (*name, hash_input, key_version=None, hash_algorithm=None, context=None, prehashed=None, signature_algorithm=None, marshaling_algorithm=None, mount_point='transit'*)

Return the cryptographic signature of the given data using the named key and the specified hash algorithm.

The key must be of a type that supports signing.

Supported methods: POST: `/{mount_point}/sign/{name}/{hash_algorithm}`). Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the encryption key to use for signing. This is specified as part of the URL.
- **hash_input** (*str | unicode*) – Specifies the base64 encoded input data.
- **key_version** (*int*) – Specifies the version of the key to use for signing. If not set, uses the latest version. Must be greater than or equal to the key’s `min_encryption_version`, if set.
- **hash_algorithm** (*str | unicode*) – Specifies the hash algorithm to use for supporting key types (notably, not including `ed25519` which specifies its own hash algorithm). This can also be specified as part of the URL. Currently-supported algorithms are: `sha2-224`, `sha2-256`, `sha2-384`, `sha2-512`
- **context** (*str | unicode*) – Base64 encoded context for key derivation. Required if key derivation is enabled; currently only available with `ed25519` keys.
- **prehashed** (*bool*) – Set to true when the input is already hashed. If the key type is `rsa-2048` or `rsa-4096`, then the algorithm used to hash the input should be indicated by the `hash_algorithm` parameter. Just as the value to sign should be the base64-encoded representation of the exact binary data you want signed, when set, input is expected to be base64-encoded binary hashed data, not hex-formatted. (As an example, on the command line, you could generate a suitable input via `openssl dgst -sha256 -binary | base64`.)
- **signature_algorithm** (*str | unicode*) – When using a RSA key, specifies the RSA signature algorithm to use for signing. Supported signature types are: `pss`, `pkcs1v15`
- **marshaling_algorithm** (*str | unicode*) – Specifies the way in which the signature should be marshaled. This currently only applies to ECDSA keys. Supported types are: `asn1`, `jws`
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type `requests.Response`

trim_key (*name, min_version, mount_point='transit'*)

Trims older key versions setting a minimum version for the keyring.

Once trimmed, previous versions of the key cannot be recovered.

Supported methods: POST: `/{mount_point}/keys/{name}/trim`. Produces: 200 application/json

Parameters

- **name** (*str | unicode*) – Specifies the name of the key to be trimmed.
- **min_version** (*int*) – The minimum version for the key ring. All versions before this version will be permanently deleted. This value can at most be equal to the lesser of `min_decryption_version` and `min_encryption_version`. This is not allowed to be set when either `min_encryption_version` or `min_decryption_version` is set to zero.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

update_key_configuration (*name*, *min_encryption_version=None*, *min_decryption_version=None*, *exportable=None*, *deletion_allowed=None*, *allow_plaintext_backup=None*, *mount_point='transit'*)

Tune configuration values for a given key.

These values are returned during a read operation on the named key.

Supported methods: POST: `/{{mount_point}}/keys/{{name}}/config`. Produces: 204 (empty body)

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key to update configuration for.
- **min_decryption_version** (*int*) – Specifies the minimum version of ciphertext allowed to be decrypted. Adjusting this as part of a key rotation policy can prevent old copies of ciphertext from being decrypted, should they fall into the wrong hands. For signatures, this value controls the minimum version of signature that can be verified against. For HMACs, this controls the minimum version of a key allowed to be used as the key for verification.
- **min_encryption_version** (*int*) – Specifies the minimum version of the key that can be used to encrypt plaintext, sign payloads, or generate HMACs. Must be 0 (which will use the latest version) or a value greater or equal to `min_decryption_version`.
- **deletion_allowed** (*bool*) – Specifies if the key is allowed to be deleted.
- **exportable** (*bool*) – Enables keys to be exportable. This allows for all the valid keys in the key ring to be exported. Once set, this cannot be disabled.
- **allow_plaintext_backup** (*bool*) – If set, enables taking backup of named key in the plaintext format. Once set, this cannot be disabled.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type `requests.Response`

verify_signed_data (*name*, *hash_input*, *signature=None*, *hmac=None*, *hash_algorithm=None*, *context=None*, *prehashed=None*, *signature_algorithm=None*, *marshaling_algorithm=None*, *mount_point='transit'*)

Return whether the provided signature is valid for the given data.

Supported methods: POST: `/{{mount_point}}/verify/{{name}}/{{hash_algorithm}}`. Produces: 200 application/json

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the encryption key that was used to generate the signature or HMAC.
- **hash_input** – Specifies the base64 encoded input data.
- **signature** (*str* | *unicode*) – Specifies the signature output from the `/transit/sign` function. Either this must be supplied or `hmac` must be supplied.
- **hmac** (*str* | *unicode*) – Specifies the signature output from the `/transit/hmac` function. Either this must be supplied or `signature` must be supplied.

- **hash_algorithm** (*str | unicode*) – Specifies the hash algorithm to use. This can also be specified as part of the URL. Currently-supported algorithms are: sha2-224, sha2-256, sha2-384, sha2-512
- **context** (*str | unicode*) – Base64 encoded context for key derivation. Required if key derivation is enabled; currently only available with ed25519 keys.
- **prehashed** (*bool*) – Set to true when the input is already hashed. If the key type is rsa-2048 or rsa-4096, then the algorithm used to hash the input should be indicated by the hash_algorithm parameter.
- **signature_algorithm** (*str | unicode*) – When using a RSA key, specifies the RSA signature algorithm to use for signature verification. Supported signature types are: pss, pkcs1v15
- **marshaling_algorithm** (*str | unicode*) – Specifies the way in which the signature should be marshaled. This currently only applies to ECDSA keys. Supported types are: asn1, jws
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The JSON response of the request.

Return type requests.Response

```
class hvac.api.secrets_engines.SecretsEngines(adapter)
    Bases: hvac.api.vault_api_category.VaultApiCategory
    Secrets Engines.
```

```
    implemented_classes = [<class 'hvac.api.secrets_engines.aws.Aws'>, <class 'hvac.api.secrets_engines.azure.Azure'>, <class 'hvac.api.secrets_engines.gcpkms.GcpKms'>, <class 'hvac.api.secrets_engines.nomad.Nomad'>, <class 'hvac.api.secrets_engines.ssh.Ssh'>, <class 'hvac.api.secrets_engines.totp.Totp'>, <class 'hvac.api.secrets_engines.cassandra.Cassandra'>]
    unimplemented_classes = ['AliCloud', 'Azure', 'GcpKms', 'Nomad', 'Ssh', 'TOTP', 'Cassandra']
```

```
class hvac.api.secrets_engines.Database(adapter)
    Bases: hvac.api.vault_api_base.VaultApiBase
    Database Secrets Engine (API).
```

Reference: <https://www.vaultproject.io/api/secret/databases/index.html>

```
configure(name, plugin_name, verify_connection=None, allowed_roles=None,
           root_rotation_statements=None, mount_point='database', *args, **kwargs)
```

This endpoint configures the connection string used to communicate with the desired database. In addition to the parameters listed here, each Database plugin has additional, database plugin specific, parameters for this endpoint. Please read the HTTP API for the plugin you’d wish to configure to see the full list of additional parameters.

Parameters

- **name** (*str | unicode*) – Specifies the name for this database connection. This is specified as part of the URL.
- **plugin_name** (*str | unicode*) – Specifies the name of the plugin to use for this connection.
- **verify_connection** (*bool*) – Specifies if the connection is verified during initial configuration.
- **allowed_roles** (*list*) – List of the roles allowed to use this connection. Defaults to empty (no roles), if contains a “*” any role can use this connection.
- **root_rotation_statements** (*list*) – Specifies the database statements to be executed to rotate the root user’s credentials.

Returns The response of the request.

Return type requests.Response

create_role (*name*, *db_name*, *creation_statements*, *default_ttl=None*, *max_ttl=None*, *revocation_statements=None*, *rollback_statements=None*, *renew_statements=None*, *mount_point='database'*)

This endpoint creates or updates a role definition.

Parameters

- **name** (*str* | *unicode*) – Specifies the database role to manage.
- **db_name** (*str* | *unicode*) – The name of the database connection to use for this role.
- **creation_statements** (*list*) – Specifies the database statements executed to create and configure a user.
- **default_ttl** (*int*) – Specifies the TTL for the leases associated with this role.
- **max_ttl** (*int*) – Specifies the maximum TTL for the leases associated with this role.
- **revocation_statements** (*list*) – Specifies the database statements to be executed to revoke a user.
- **rollback_statements** (*list*) – Specifies the database statements to be executed to rollback a create operation in the event of an error.
- **renew_statements** (*list*) – Specifies the database statements to be executed to renew a user.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

delete_connection (*name*, *mount_point='database'*)

This endpoint deletes a connection.

Parameters **name** (*str* | *unicode*) – Specifies the name of the connection to delete.

Returns The response of the request.

Return type requests.Response

delete_role (*name*, *mount_point='database'*)

This endpoint deletes the role definition.

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the role to delete.
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

generate_credentials (*name*, *mount_point='database'*)

This endpoint generates a new set of dynamic credentials based on the named role.

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the role to create credentials against
- **mount_point** (*str* | *unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

list_connections (*mount_point='database'*)

This endpoint returns a list of available connections.

Returns The response of the request.

Return type requests.Response

list_roles (*mount_point='database'*)

This endpoint returns a list of available roles.

Parameters **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

read_connection (*name, mount_point='database'*)

This endpoint returns the configuration settings for a connection.

Parameters **name** (*str | unicode*) – Specifies the name of the connection to read.

Returns The response of the request.

Return type requests.Response

read_role (*name, mount_point='database'*)

This endpoint queries the role definition.

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to read.
- **mount_point** (*str | unicode*) – The “path” the method/backend was mounted on.

Returns The response of the request.

Return type requests.Response

reset_connection (*name, mount_point='database'*)

This endpoint closes a connection and it’s underlying plugin and restarts it with the configuration stored in the barrier.

Parameters **name** (*str | unicode*) – Specifies the name of the connection to reset.

Returns The response of the request.

Return type requests.Response

rotate_root_credentials (*name, mount_point='database'*)

This endpoint is used to rotate the root superuser credentials stored for the database connection. This user must have permissions to update its own password.

Parameters **name** (*str | unicode*) – Specifies the name of the connection to rotate.

Returns The response of the request.

Return type requests.Response

class hvac.api.secrets_engines.**RabbitMQ** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

RabbitMQ Secrets Engine (API). Reference: <https://www.vaultproject.io/api/secret/rabbitmq/index.html>

configure (*connection_uri*=", *username*=", *password*=", *verify_connection*=True, *mount_point*='rabbitmq')

Configure shared information for the rabbitmq secrets engine.

Supported methods: POST: /{mount_point}/config/connection. Produces: 204 (empty body)

Parameters

- **connection_uri** (*str* | *unicode*) – Specifies the RabbitMQ connection URI.
- **username** (*str* | *unicode*) – Specifies the RabbitMQ management administrator username.
- **mount_point** (*str* | *unicode*) – Specifies the place where the secrets engine will be accessible (default: rabbitmq).

Password Specifies the RabbitMQ management administrator password.

Verify_connection Specifies whether to verify connection URI, username, and password.

Returns The response of the request.

Return type requests.Response

configure_lease (*ttl*, *max_ttl*, *mount_point*='rabbitmq')

This endpoint configures the lease settings for generated credentials.

Parameters

- **ttl** (*int*) – Specifies the lease ttl provided in seconds.
- **max_ttl** (*int*) – Specifies the maximum ttl provided in seconds.
- **mount_point** (*str* | *unicode*) – Specifies the place where the secrets engine will be accessible (default: rabbitmq).

Returns The JSON response of the request.

Return type requests.Response

create_role (*name*, *tags*=", *vhosts*=", *mount_point*='rabbitmq')

This endpoint creates or updates the role definition.

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the role to create.
- **tags** (*str* | *unicode*) – Specifies a comma-separated RabbitMQ management tags.
- **vhosts** (*str* | *unicode*) – Specifies a map of virtual hosts to permissions.
- **mount_point** (*str* | *unicode*) – Specifies the place where the secrets engine will be accessible (default: rabbitmq).

Returns The JSON response of the request.

Return type requests.Response

delete_role (*name*, *mount_point*='rabbitmq')

This endpoint deletes the role definition. Even if the role does not exist, this endpoint will still return a successful response.

Parameters

- **name** (*str* | *unicode*) – Specifies the name of the role to delete.

- **mount_point** (*str | unicode*) – Specifies the place where the secrets engine will be accessible (default: rabbitmq).

Returns The response of the request.

Return type requests.Response

generate_credentials (*name, mount_point='rabbitmq'*)

This endpoint generates a new set of dynamic credentials based on the named role.

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to create credentials against.
- **mount_point** (*str | unicode*) – Specifies the place where the secrets engine will be accessible (default: rabbitmq).

Returns The response of the request.

Return type requests.Response

read_role (*name, mount_point='rabbitmq'*)

This endpoint queries the role definition.

Parameters

- **name** (*str | unicode*) – Specifies the name of the role to read.
- **mount_point** (*str | unicode*) – Specifies the place where the secrets engine will be accessible (default: rabbitmq).

Returns The JSON response of the request.

Return type requests.Response

4.5 hvac.api.system_backend

Collection of Vault system backend API endpoint classes.

class hvac.api.system_backend.Audit (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

calculate_hash (*path, input_to_hash*)

Hash the given input data with the specified audit device's hash function and salt.

This endpoint can be used to discover whether a given plaintext string (the input parameter) appears in the audit log in obfuscated form.

Supported methods: POST: /sys/audit-hash/{path}. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – The path of the audit device to generate hashes for. This is part of the request URL.
- **input_to_hash** (*str | unicode*) – The input string to hash.

Returns The JSON response of the request.

Return type requests.Response

disable_audit_device (*path*)

Disable the audit device at the given path.

Supported methods: DELETE: /sys/audit/{path}. Produces: 204 (empty body)

Parameters `path` (*str | unicode*) – The path of the audit device to delete. This is part of the request URL.

Returns The response of the request.

Return type requests.Response

enable_audit_device (*device_type, description=None, options=None, path=None, local=None*)
Enable a new audit device at the supplied path.

The path can be a single word name or a more complex, nested path.

Supported methods: PUT: /sys/audit/{path}. Produces: 204 (empty body)

Parameters

- **device_type** (*str | unicode*) – Specifies the type of the audit device.
- **description** (*str | unicode*) – Human-friendly description of the audit device.
- **options** (*str | unicode*) – Configuration options to pass to the audit device itself. This is dependent on the audit device type.
- **path** (*str | unicode*) – Specifies the path in which to enable the audit device. This is part of the request URL.
- **local** (*bool*) – Specifies if the audit device is a local only.

Returns The response of the request.

Return type requests.Response

list_enabled_audit_devices ()

List enabled audit devices.

It does not list all available audit devices. This endpoint requires sudo capability in addition to any path-specific capabilities.

Supported methods: GET: /sys/audit. Produces: 200 application/json

Returns JSON response of the request.

Return type dict

class hvac.api.system_backend.Auth (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

disable_auth_method (*path*)

Disable the auth method at the given auth path.

Supported methods: DELETE: /sys/auth/{path}. Produces: 204 (empty body)

Parameters `path` (*str | unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.

Returns The response of the request.

Return type requests.Response

enable_auth_method (*method_type*, *description=None*, *config=None*, *plugin_name=None*, *local=False*, *path=None*, ***kwargs*)

Enable a new auth method.

After enabling, the auth method can be accessed and configured via the auth path specified as part of the URL. This auth path will be nested under the auth prefix.

Supported methods: POST: /sys/auth/{path}. Produces: 204 (empty body)

Parameters

- **method_type** (*str* | *unicode*) – The name of the authentication method type, such as “github” or “token”.
- **description** (*str* | *unicode*) – A human-friendly description of the auth method.
- **config** (*dict*) – Configuration options for this auth method. These are the possible values:
 - **default_lease_ttl**: The default lease duration, specified as a string duration like “5s” or “30m”.
 - **max_lease_ttl**: The maximum lease duration, specified as a string duration like “5s” or “30m”.
 - **audit_non_hmac_request_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the request data object.
 - **audit_non_hmac_response_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the response data object.
 - **listing_visibility**: Specifies whether to show this mount in the UI-specific listing endpoint.
 - **passthrough_request_headers**: Comma-separated list of headers to whitelist and pass from the request to the backend.
- **plugin_name** (*str* | *unicode*) – The name of the auth plugin to use based from the name in the plugin catalog. Applies only to plugin methods.
- **local** (*bool*) – <Vault enterprise only> Specifies if the auth method is a local only. Local auth methods are not replicated nor (if a secondary) removed by replication.
- **path** (*str* | *unicode*) – The path to mount the method on. If not provided, defaults to the value of the “method_type” argument.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

list_auth_methods ()

List all enabled auth methods.

Supported methods: GET: /sys/auth. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

read_auth_method_tuning (*path*)

Read the given auth path's configuration.

This endpoint requires sudo capability on the final path, but the same functionality can be achieved without sudo via `sys/mounts/auth/[auth-path]/tune`.

Supported methods: GET: `/sys/auth/{path}/tune`. Produces: 200 application/json

Parameters `path` (*str | unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.

Returns The JSON response of the request.

Return type dict

tune_auth_method (*path*, *default_lease_ttl=None*, *max_lease_ttl=None*, *description=None*, *audit_non_hmac_request_keys=None*, *audit_non_hmac_response_keys=None*, *listing_visibility=None*, *passthrough_request_headers=None*, ***kwargs*)

Tune configuration parameters for a given auth path.

This endpoint requires sudo capability on the final path, but the same functionality can be achieved without sudo via `sys/mounts/auth/[auth-path]/tune`.

Supported methods: POST: `/sys/auth/{path}/tune`. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – The path the method was mounted on. If not provided, defaults to the value of the “method_type” argument.
- **default_lease_ttl** (*int*) – Specifies the default time-to-live. If set on a specific auth path, this overrides the global default.
- **max_lease_ttl** (*int*) – The maximum time-to-live. If set on a specific auth path, this overrides the global default.
- **description** (*str | unicode*) – Specifies the description of the mount. This overrides the current stored value, if any.
- **audit_non_hmac_request_keys** (*array*) – Specifies the list of keys that will not be HMAC'd by audit devices in the request data object.
- **audit_non_hmac_response_keys** (*list*) – Specifies the list of keys that will not be HMAC'd by audit devices in the response data object.
- **listing_visibility** (*list*) – Specifies whether to show this mount in the UI-specific listing endpoint. Valid values are “unauth” or “”.
- **passthrough_request_headers** (*list*) – List of headers to whitelist and pass from the request to the backend.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

class hvac.api.system_backend.Capabilities (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

get_capabilities (*paths*, *token=None*, *accessor=None*)

Get the capabilities associated with a token.

Supported methods: POST: /sys/capabilities-self. Produces: 200 application/json POST: /sys/capabilities. Produces: 200 application/json POST: /sys/capabilities-accessor. Produces: 200 application/json

Parameters

- **paths** (*List[str]*) – Paths on which capabilities are being queried.
- **token** (*str*) – Token for which capabilities are being queried.
- **accessor** (*str*) – Accessor of the token for which capabilities are being queried.

Returns The JSON response of the request.

Return type dict

class hvac.api.system_backend.**Health** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

Reference: <https://www.vaultproject.io/api/system/index.html>

read_health_status (*standby_ok=None, active_code=None, standby_code=None, dr_secondary_code=None, performance_standby_code=None, sealed_code=None, uninit_code=None, method='HEAD'*)

Read the health status of Vault.

This matches the semantics of a Consul HTTP health check and provides a simple way to monitor the health of a Vault instance.

Parameters

- **standby_ok** (*bool*) – Specifies if being a standby should still return the active status code instead of the standby status code. This is useful when Vault is behind a non-configurable load balance that just wants a 200-level response.
- **active_code** (*int*) – The status code that should be returned for an active node.
- **standby_code** (*int*) – Specifies the status code that should be returned for a standby node.
- **dr_secondary_code** (*int*) – Specifies the status code that should be returned for a DR secondary node.
- **performance_standby_code** (*int*) – Specifies the status code that should be returned for a performance standby node.
- **sealed_code** (*int*) – Specifies the status code that should be returned for a sealed node.
- **uninit_code** (*int*) – Specifies the status code that should be returned for a uninitialized node.
- **method** (*str | unicode*) – Supported methods: HEAD: /sys/health. Produces: 000 (empty body) GET: /sys/health. Produces: 000 application/json

Returns The JSON response of the request.

Return type requests.Response

class hvac.api.system_backend.**Init** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

initialize (*secret_shares=5, secret_threshold=3, pgp_keys=None, root_token_pgp_key=None, stored_shares=None, recovery_shares=None, recovery_threshold=None, recovery_pgp_keys=None*)

Initialize a new Vault.

The Vault must not have been previously initialized. The recovery options, as well as the stored shares option, are only available when using Vault HSM.

Supported methods: PUT: /sys/init. Produces: 200 application/json

Parameters

- **secret_shares** (*int*) – The number of shares to split the master key into.
- **secret_threshold** (*int*) – Specifies the number of shares required to reconstruct the master key. This must be less than or equal secret_shares. If using Vault HSM with auto-unsealing, this value must be the same as secret_shares.
- **pgp_keys** (*list*) – List of PGP public keys used to encrypt the output unseal keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as secret_shares.
- **root_token_pgp_key** (*str | unicode*) – Specifies a PGP public key used to encrypt the initial root token. The key must be base64-encoded from its original binary representation.
- **stored_shares** (*int*) – <enterprise only> Specifies the number of shares that should be encrypted by the HSM and stored for auto-unsealing. Currently must be the same as secret_shares.
- **recovery_shares** (*int*) – <enterprise only> Specifies the number of shares to split the recovery key into.
- **recovery_threshold** (*int*) – <enterprise only> Specifies the number of shares required to reconstruct the recovery key. This must be less than or equal to recovery_shares.
- **recovery_pgp_keys** (*list*) – <enterprise only> Specifies an array of PGP public keys used to encrypt the output recovery keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as recovery_shares.

Returns The JSON response of the request.

Return type dict

is_initialized ()

Determine is Vault is initialized or not.

Returns True if Vault is initialized, False otherwise.

Return type bool

read_init_status ()

Read the initialization status of Vault.

Supported methods: GET: /sys/init. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

class hvac.api.system_backend.**Key** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

cancel_rekey (*recovery_key=False*)

Cancel any in-progress rekey.

This clears the rekey settings as well as any progress made. This must be called to change the parameters of the rekey.

Note: Verification is still a part of a rekey. If rekeying is canceled during the verification flow, the current unseal keys remain valid.

Supported methods: DELETE: /sys/rekey/init. Produces: 204 (empty body) DELETE: /sys/rekey-recovery-key/init. Produces: 204 (empty body)

Parameters **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The response of the request.

Return type requests.Response

cancel_root_generation ()

Cancel any in-progress root generation attempt.

This clears any progress made. This must be called to change the OTP or PGP key being used.

Supported methods: DELETE: /sys/generate-root/attempt. Produces: 204 (empty body)

Returns The response of the request.

Return type request.Response

generate_root (*key, nonce*)

Enter a single master key share to progress the root generation attempt.

If the threshold number of master key shares is reached, Vault will complete the root generation and issue the new token. Otherwise, this API must be called multiple times until that threshold is met. The attempt nonce must be provided with each call.

Supported methods: PUT: /sys/generate-root/update. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single master key share.
- **nonce** (*str | unicode*) – The nonce of the attempt.

Returns The JSON response of the request.

Return type dict

get_encryption_key_status ()

Read information about the current encryption key used by Vault.

Supported methods: GET: /sys/key-status. Produces: 200 application/json

Returns JSON response with information regarding the current encryption key used by Vault.

Return type dict

read_backup_keys (*recovery_key=False*)

Retrieve the backup copy of PGP-encrypted unseal keys.

The returned value is the nonce of the rekey operation and a map of PGP key fingerprint to hex-encoded PGP-encrypted key.

Supported methods: PUT: /sys/rekey/backup. Produces: 200 application/json PUT: /sys/rekey-recovery-key/backup. Produces: 200 application/json

Parameters **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type dict

read_rekey_progress (*recovery_key=False*)

Read the configuration and progress of the current rekey attempt.

Supported methods: GET: /sys/rekey-recovery-key/init. Produces: 200 application/json GET: /sys/rekey/init. Produces: 200 application/json

Parameters **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type requests.Response

read_root_generation_progress ()

Read the configuration and process of the current root generation attempt.

Supported methods: GET: /sys/generate-root/attempt. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

rekey (*key, nonce=None, recovery_key=False*)

Enter a single recovery key share to progress the rekey of the Vault.

If the threshold number of recovery key shares is reached, Vault will complete the rekey. Otherwise, this API must be called multiple times until that threshold is met. The rekey nonce operation must be provided with each call.

Supported methods: PUT: /sys/rekey/update. Produces: 200 application/json PUT: /sys/rekey-recovery-key/update. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single recovery share key.
- **nonce** (*str | unicode*) – Specifies the nonce of the rekey operation.
- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON response of the request.

Return type dict

rekey_multi (*keys, nonce=None, recovery_key=False*)

Enter multiple recovery key shares to progress the rekey of the Vault.

If the threshold number of recovery key shares is reached, Vault will complete the rekey.

Parameters

- **keys** (*list*) – Specifies multiple recovery share keys.
- **nonce** (*str | unicode*) – Specifies the nonce of the rekey operation.
- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The last response of the rekey request.

Return type response.Request

rotate_encryption_key ()

Trigger a rotation of the backend encryption key.

This is the key that is used to encrypt data written to the storage backend, and is not provided to operators. This operation is done online. Future values are encrypted with the new key, while old values are decrypted with previous encryption keys.

This path requires sudo capability in addition to update.

Supported methods: PUT: /sys/rorate. Produces: 204 (empty body)

Returns The response of the request.

Return type requests.Response

start_rekey (*secret_shares=5, secret_threshold=3, pgp_keys=None, backup=False, require_verification=False, recovery_key=False*)

Initializes a new rekey attempt.

Only a single recovery key rekeyattempt can take place at a time, and changing the parameters of a rekey requires canceling and starting a new rekey, which will also provide a new nonce.

Supported methods: PUT: /sys/rekey/init. Produces: 204 (empty body) PUT: /sys/rekey-recovery-key/init. Produces: 204 (empty body)

Parameters

- **secret_shares** (*int*) – Specifies the number of shares to split the master key into.
- **secret_threshold** (*int*) – Specifies the number of shares required to reconstruct the master key. This must be less than or equal to secret_shares.
- **pgp_keys** (*list*) – Specifies an array of PGP public keys used to encrypt the output unseal keys. Ordering is preserved. The keys must be base64-encoded from their original binary representation. The size of this array must be the same as secret_shares.
- **backup** (*bool*) – Specifies if using PGP-encrypted keys, whether Vault should also store a plaintext backup of the PGP-encrypted keys at core/unseal-keys-backup in the physical storage backend. These can then be retrieved and removed via the sys/rekey/backup endpoint.
- **require_verification** (*bool*) – This turns on verification functionality. When verification is turned on, after successful authorization with the current unseal keys, the new unseal keys are returned but the master key is not actually rotated. The new keys must be provided to authorize the actual rotation of the master key. This ensures that the new keys have been successfully saved and protects against a risk of the keys being lost after rotation but before they can be persisted. This can be used with without pgp_keys, and when used with it, it allows ensuring that the returned keys can be successfully decrypted before committing to the new shares, which the backup functionality does not provide.

- **recovery_key** (*bool*) – If true, send requests to “rekey-recovery-key” instead of “rekey” api path.

Returns The JSON dict of the response.

Return type dict | request.Response

start_root_token_generation (*otp=None, pgp_key=None*)

Initialize a new root generation attempt.

Only a single root generation attempt can take place at a time. One (and only one) of *otp* or *pgp_key* are required.

Supported methods: PUT: /sys/generate-root/attempt. Produces: 200 application/json

Parameters

- **otp** (*str | unicode*) – Specifies a base64-encoded 16-byte value. The raw bytes of the token will be XOR'd with this value before being returned to the final unseal key provider.
- **pgp_key** (*str | unicode*) – Specifies a base64-encoded PGP public key. The raw bytes of the token will be encrypted with this value before being returned to the final unseal key provider.

Returns The JSON response of the request.

Return type dict

class hvac.api.system_backend.**Leader** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

read_leader_status ()

Read the high availability status and current leader instance of Vault.

Supported methods: GET: /sys/leader. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

class hvac.api.system_backend.**Lease** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

list_leases (*prefix*)

Retrieve a list of lease ids.

Supported methods: LIST: /sys/leases/lookup/{prefix}. Produces: 200 application/json

Parameters **prefix** (*str | unicode*) – Lease prefix to filter list by.

Returns The JSON response of the request.

Return type dict

read_lease (*lease_id*)

Retrieve lease metadata.

Supported methods: PUT: /sys/leases/lookup. Produces: 200 application/json

Parameters **lease_id** (*str | unicode*) – the ID of the lease to lookup.

Returns Parsed JSON response from the leases PUT request

Return type dict.

renew_lease (*lease_id*, *increment=None*)

Renew a lease, requesting to extend the lease.

Supported methods: PUT: /sys/leases/renew. Produces: 200 application/json

Parameters

- **lease_id** (*str* | *unicode*) – The ID of the lease to extend.
- **increment** (*int*) – The requested amount of time (in seconds) to extend the lease.

Returns The JSON response of the request

Return type dict

revoke_force (*prefix*)

Revoke all secrets or tokens generated under a given prefix immediately.

Unlike `revoke_prefix`, this path ignores backend errors encountered during revocation. This is potentially very dangerous and should only be used in specific emergency situations where errors in the backend or the connected backend service prevent normal revocation.

Supported methods: PUT: /sys/leases/revoke-force/{prefix}. Produces: 204 (empty body)

Parameters **prefix** (*str* | *unicode*) – The prefix to revoke.

Returns The response of the request.

Return type requests.Response

revoke_lease (*lease_id*)

Revoke a lease immediately.

Supported methods: PUT: /sys/leases/revoke. Produces: 204 (empty body)

Parameters **lease_id** (*str* | *unicode*) – Specifies the ID of the lease to revoke.

Returns The response of the request.

Return type requests.Response

revoke_prefix (*prefix*)

Revoke all secrets (via a lease ID prefix) or tokens (via the tokens' path property) generated under a given prefix immediately.

This requires sudo capability and access to it should be tightly controlled as it can be used to revoke very large numbers of secrets/tokens at once.

Supported methods: PUT: /sys/leases/revoke-prefix/{prefix}. Produces: 204 (empty body)

Parameters **prefix** (*str* | *unicode*) – The prefix to revoke.

Returns The response of the request.

Return type requests.Response

class hvac.api.system_backend.**Mount** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

disable_secrets_engine (*path*)

Disable the mount point specified by the provided path.

Supported methods: DELETE: /sys/mounts/{path}. Produces: 204 (empty body)

Parameters **path** (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.

Returns The response of the request.

Return type requests.Response

enable_secrets_engine (*backend_type, path=None, description=None, config=None, plugin_name=None, options=None, local=False, seal_wrap=False, **kwargs*)

Enable a new secrets engine at the given path.

Supported methods: POST: /sys/mounts/{path}. Produces: 204 (empty body)

Parameters

- **backend_type** (*str | unicode*) – The name of the backend type, such as “github” or “token”.
- **path** (*str | unicode*) – The path to mount the method on. If not provided, defaults to the value of the “method_type” argument.
- **description** (*str | unicode*) – A human-friendly description of the mount.
- **config** (*dict*) – Configuration options for this mount. These are the possible values:
 - **default_lease_ttl**: The default lease duration, specified as a string duration like “5s” or “30m”.
 - **max_lease_ttl**: The maximum lease duration, specified as a string duration like “5s” or “30m”.
 - **force_no_cache**: Disable caching.
 - **plugin_name**: The name of the plugin in the plugin catalog to use.
 - **audit_non_hmac_request_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the request data object.
 - **audit_non_hmac_response_keys**: Comma-separated list of keys that will not be HMAC’d by audit devices in the response data object.
 - **listing_visibility**: Specifies whether to show this mount in the UI-specific listing endpoint. (“unauth” or “hidden”)
 - **passthrough_request_headers**: Comma-separated list of headers to whitelist and pass from the request to the backend.
- **options** (*dict*) – Specifies mount type specific options that are passed to the backend.
 - **version**: <KV> The version of the KV to mount. Set to “2” for mount KV v2.
- **plugin_name** (*str | unicode*) – Specifies the name of the plugin to use based from the name in the plugin catalog. Applies only to plugin backends.
- **local** (*bool*) – <Vault enterprise only> Specifies if the auth method is a local only. Local auth methods are not replicated nor (if a secondary) removed by replication.
- **seal_wrap** (*bool*) – <Vault enterprise only> Enable seal wrapping for the mount.

- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response of the request.

Return type requests.Response

list_mounted_secrets_engines ()

Lists all the mounted secrets engines.

Supported methods: POST: /sys/mounts. Produces: 200 application/json

Returns JSON response of the request.

Return type dict

move_backend (*from_path, to_path*)

Move an already-mounted backend to a new mount point.

Supported methods: POST: /sys/remount. Produces: 204 (empty body)

Parameters

- **from_path** (*str | unicode*) – Specifies the previous mount point.
- **to_path** (*str | unicode*) – Specifies the new destination mount point.

Returns The response of the request.

Return type requests.Response

read_mount_configuration (*path*)

Read the given mount's configuration.

Unlike the mounts endpoint, this will return the current time in seconds for each TTL, which may be the system default or a mount-specific value.

Supported methods: GET: /sys/mounts/{path}/tune. Produces: 200 application/json

Parameters **path** (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.

Returns The JSON response of the request.

Return type requests.Response

retrieve_mount_option (*mount_point, option_name, default_value=None*)

tune_mount_configuration (*path, default_lease_ttl=None, max_lease_ttl=None, description=None, audit_non_hmac_request_keys=None, audit_non_hmac_response_keys=None, listing_visibility=None, passthrough_request_headers=None, options=None, force_no_cache=None, **kwargs*)

Tune configuration parameters for a given mount point.

Supported methods: POST: /sys/mounts/{path}/tune. Produces: 204 (empty body)

Parameters

- **path** (*str | unicode*) – Specifies the path where the secrets engine will be mounted. This is specified as part of the URL.
- **mount_point** (*str*) – The path the associated secret backend is mounted

- **description** (*str*) – Specifies the description of the mount. This overrides the current stored value, if any.
- **default_lease_ttl** (*int*) – Default time-to-live. This overrides the global default. A value of 0 is equivalent to the system default TTL
- **max_lease_ttl** (*int*) – Maximum time-to-live. This overrides the global default. A value of 0 are equivalent and set to the system max TTL.
- **audit_non_hmac_request_keys** (*list*) – Specifies the comma-separated list of keys that will not be HMAC'd by audit devices in the request data object.
- **audit_non_hmac_response_keys** (*list*) – Specifies the comma-separated list of keys that will not be HMAC'd by audit devices in the response data object.
- **listing_visibility** (*str*) – Specifies whether to show this mount in the UI-specific listing endpoint. Valid values are “unauth” or “”.
- **passthrough_request_headers** (*str*) – Comma-separated list of headers to whitelist and pass from the request to the backend.
- **options** (*dict*) – Specifies mount type specific options that are passed to the backend.
 - **version**: <KV> The version of the KV to mount. Set to “2” for mount KV v2.
- **force_no_cache** (*bool*) – Disable caching.
- **kwargs** (*dict*) – All dicts are accepted and passed to vault. See your specific secret engine for details on which extra key-word arguments you might want to pass.

Returns The response from the request.

Return type request.Response

class hvac.api.system_backend.Namespace (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

create_namespace (*path*)

Create a namespace at the given path.

Supported methods: POST: /sys/namespaces/{path}. Produces: 200 application/json

Returns The response of the request.

Return type requests.Response

delete_namespace (*path*)

Delete a namespaces. You cannot delete a namespace with existing child namespaces.

Supported methods: DELETE: /sys/namespaces. Produces: 204 (empty body)

Returns The response of the request.

Return type requests.Response

list_namespaces ()

Lists all the namespaces.

Supported methods: LIST: /sys/namespaces. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

class hvac.api.system_backend.**Policy** (*adapter*)
 Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

create_or_update_policy (*name, policy, pretty_print=True*)
 Add a new or update an existing policy.
 Once a policy is updated, it takes effect immediately to all associated users.
Supported methods: PUT: /sys/policy/{name}. Produces: 204 (empty body)

Parameters

- **name** (*str | unicode*) – Specifies the name of the policy to create.
- **policy** (*str | unicode | dict*) – Specifies the policy document.
- **pretty_print** (*bool*) – If True, and provided a dict for the policy argument, send the policy JSON to Vault with “pretty” formatting.

Returns The response of the request.
Return type requests.Response

delete_policy (*name*)
 Delete the policy with the given name.
 This will immediately affect all users associated with this policy.
Supported methods: DELETE: /sys/policy/{name}. Produces: 204 (empty body)

Parameters **name** (*str | unicode*) – Specifies the name of the policy to delete.
Returns The response of the request.
Return type requests.Response

list_policies ()
 List all configured policies.
Supported methods: GET: /sys/policy. Produces: 200 application/json

Returns The JSON response of the request.
Return type dict

read_policy (*name*)
 Retrieve the policy body for the named policy.
Supported methods: GET: /sys/policy/{name}. Produces: 200 application/json

Parameters **name** (*str | unicode*) – The name of the policy to retrieve.
Returns The response of the request
Return type dict

class hvac.api.system_backend.**Seal** (*adapter*)
 Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

is_sealed ()
 Determine if Vault is sealed.
Returns True if Vault is seal, False otherwise.

Return type bool

read_seal_status ()

Read the seal status of the Vault.

This is an unauthenticated endpoint.

Supported methods: GET: /sys/seal-status. Produces: 200 application/json

Returns The JSON response of the request.

Return type dict

seal ()

Seal the Vault.

In HA mode, only an active node can be sealed. Standby nodes should be restarted to get the same effect. Requires a token with root policy or sudo capability on the path.

Supported methods: PUT: /sys/seal. Produces: 204 (empty body)

Returns The response of the request.

Return type requests.Response

submit_unseal_key (*key=None, reset=False, migrate=False*)

Enter a single master key share to progress the unsealing of the Vault.

If the threshold number of master key shares is reached, Vault will attempt to unseal the Vault. Otherwise, this API must be called multiple times until that threshold is met.

Either the key or reset parameter must be provided; if both are provided, reset takes precedence.

Supported methods: PUT: /sys/unseal. Produces: 200 application/json

Parameters

- **key** (*str | unicode*) – Specifies a single master key share. This is required unless reset is true.
- **reset** (*bool*) – Specifies if previously-provided unseal keys are discarded and the unseal process is reset.
- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the request.

Return type dict

submit_unseal_keys (*keys, migrate=False*)

Enter multiple master key share to progress the unsealing of the Vault.

Parameters

- **keys** (*List[str]*) – List of master key shares.
- **migrate** – Available in 1.0 Beta - Used to migrate the seal from shamir to autoseal or autoseal to shamir. Must be provided on all unseal key calls.

Type migrate: bool

Returns The JSON response of the last unseal request.

Return type dict

class hvac.api.system_backend.**SystemBackend** (*adapter*)

Bases: hvac.api.vault_api_category.VaultApiCategory, hvac.api.system_backend.audit.Audit, hvac.api.system_backend.auth.Auth, hvac.api.system_backend.capabilities.Capabilities, hvac.api.system_backend.health.Health, hvac.api.system_backend.init.Init, hvac.api.system_backend.key.Key, hvac.api.system_backend.leader.Leader, hvac.api.system_backend.lease.Lease, hvac.api.system_backend.mount.Mount, hvac.api.system_backend.namespace.Namespace, hvac.api.system_backend.policy.Policy, hvac.api.system_backend.seal.Seal, hvac.api.system_backend.wrapping.Wrapping

__init__ (*adapter*)

API Category class constructor.

Parameters *adapter* (hvac.adapters.Adapter) – Instance of *hvac.adapters.Adapter*; used for performing HTTP requests.

implemented_classes = [`<class 'hvac.api.system_backend.audit.Audit'>`, `<class 'hvac.api`

`unimplemented_classes` = []

class hvac.api.system_backend.**SystemBackendMixin** (*adapter*)

Bases: hvac.api.vault_api_base.VaultApiBase

Base class for System Backend API endpoints.

class hvac.api.system_backend.**Wrapping** (*adapter*)

Bases: hvac.api.system_backend.system_backend_mixin.SystemBackendMixin

unwrap (*token=None*)

Return the original response inside the given wrapping token.

Unlike simply reading cubbyhole/response (which is deprecated), this endpoint provides additional validation checks on the token, returns the original value on the wire rather than a JSON string representation of it, and ensures that the response is properly audit-logged.

Supported methods: POST: /sys/wrapping/unwrap. Produces: 200 application/json

Parameters *token* (*str* | *unicode*) – Specifies the wrapping token ID. This is required if the client token is not the wrapping token. Do not use the wrapping token in both locations.

Returns The JSON response of the request.

Return type dict

4.6 hvac.utils

Misc utility functions and constants

hvac.utils.comma_delimited_to_list (*list_param*)

Convert comma-delimited list / string into a list of strings

Parameters *list_param* (*str* | *unicode*) – Comma-delimited string

Returns A list of strings

Return type list

`hvac.utils.deprecated_method` (*to_be_removed_in_version*, *new_method=None*)

This is a decorator which can be used to mark methods as deprecated. It will result in a warning being emitted when the function is used.

Parameters

- **to_be_removed_in_version** (*str*) – Version of this module the decorated method will be removed in.
- **new_method** (*function*) – Method intended to replace the decorated method. This method’s docstrings are included in the decorated method’s docstring.

Returns Wrapped function that includes a deprecation warning and update docstrings from the replacement method.

Return type `types.FunctionType`

`hvac.utils.format_url` (*format_str*, **args*, ***kwargs*)

Creates a URL using the specified format after escaping the provided arguments.

Parameters

- **format_str** (*str*) – The URL containing replacement fields.
- **kwargs** (*dict*) – Positional replacement field values.
- **kwargs** – Named replacement field values.

Returns The formatted URL path with escaped replacement fields.

Return type `str`

`hvac.utils.generate_method_deprecation_message` (*to_be_removed_in_version*,
old_method_name,
method_name=None, *module_name=None*)

Generate a message to be used when warning about the use of deprecated methods.

Parameters

- **to_be_removed_in_version** (*str*) – Version of this module the deprecated method will be removed in.
- **old_method_name** (*str*) – Deprecated method name.
- **method_name** (*str*) – Method intended to replace the deprecated method indicated. This method’s docstrings are included in the decorated method’s docstring.
- **module_name** (*str*) – Name of the module containing the new method to use.

Returns Full deprecation warning message for the indicated method.

Return type `str`

`hvac.utils.generate_property_deprecation_message` (*to_be_removed_in_version*,
old_name, *new_name*, *new_attribute*,
module_name='Client')

Generate a message to be used when warning about the use of deprecated properties.

Parameters

- **to_be_removed_in_version** (*str*) – Version of this module the deprecated property will be removed in.
- **old_name** (*str*) – Deprecated property name.
- **new_name** (*str*) – Name of the new property name to use.

- **new_attribute** (*str*) – The new attribute where the new property can be found.
- **module_name** (*str*) – Name of the module containing the new method to use.

Returns Full deprecation warning message for the indicated property.

Return type `str`

`hvac.utils.get_token_from_env()`

Get the token from env var, VAULT_TOKEN. If not set, attempt to get the token from, ~/.vault-token

Returns The vault token if set, else None

Return type `str | None`

`hvac.utils.getattr_with_deprecated_properties(obj, item, deprecated_properties)`

Helper method to use in the getattr method of a class with deprecated properties.

Parameters

- **obj** (*object*) – Instance of the Class containing the deprecated properties in question.
- **item** (*str*) – Name of the attribute being requested.
- **deprecated_properties** (*List[dict]*) – List of deprecated properties. Each item in the list is a dict with at least a “to_be_removed_in_version” and “client_property” key to be used in the displayed deprecation warning.

Returns The new property indicated where available.

Return type `object`

`hvac.utils.list_to_comma_delimited(list_param)`

Convert a list of strings into a comma-delimited list / string.

Parameters **list_param** (*list*) – A list of strings.

Returns Comma-delimited string.

Return type `str`

`hvac.utils.raise_for_error(status_code, message=None, errors=None)`

Helper method to raise exceptions based on the status code of a response received back from Vault.

Parameters

- **status_code** (*int*) – Status code received in a response from Vault.
- **message** (*str*) – Optional message to include in a resulting exception.
- **errors** (*list | str*) – Optional errors to include in a resulting exception.

Raises `hvac.exceptions.InvalidRequest | hvac.exceptions.Unauthorized | hvac.exceptions.Forbidden`
`| hvac.exceptions.InvalidPath | hvac.exceptions.RateLimitExceeded |`
`hvac.exceptions.InternalServerError | hvac.exceptions.VaultNotInitialized |`
`hvac.exceptions.VaultDown | hvac.exceptions.UnexpectedError`

`hvac.utils.remove_nones(params)`

Removes None values from optional arguments in a parameter dictionary.

Parameters **params** (*dict*) – The dictionary of parameters to be filtered.

Returns A filtered copy of the parameter dictionary.

Return type `dict`

`hvac.utils.validate_list_of_strings_param(param_name, param_argument)`

Validate that an argument is a list of strings.

Parameters

- **param_name** (*str | unicode*) – The name of the parameter being validated. Used in any resulting exception messages.
- **param_argument** (*list*) – The argument to validate.

Returns True if the argument is validated, False otherwise.

Return type bool

`hvac.utils.validate_pem_format(param_name, param_argument)`

Validate that an argument is a PEM-formatted public key or certificate

Parameters

- **param_name** (*str | unicode*) – The name of the parameter being validate. Used in any resulting exception messages.
- **param_argument** (*str | unicode*) – The argument to validate

Returns True if the argument is validate False otherwise

Return type bool

4.7 hvac.aws_utils

`class hvac.aws_utils.SigV4Auth(access_key, secret_key, session_token=None, region='us-east-1')`

Bases: object

`__init__(access_key, secret_key, session_token=None, region='us-east-1')`

Initialize self. See help(type(self)) for accurate signature.

`add_auth(request)`

`hvac.aws_utils.generate_sigv4_auth_request(header_value=None)`

Helper function to prepare a AWS API request to subsequently generate a “AWS Signature Version 4” header.

Parameters **header_value** (*str*) – Vault allows you to require an additional header, X-Vault-AWS-IAM-Server-ID, to be present to mitigate against different types of replay attacks. Depending on the configuration of the AWS auth backend, providing a argument to this optional parameter may be required.

Returns A PreparedRequest instance, optionally containing the provided header value under a ‘X-Vault-AWS-IAM-Server-ID’ header name pointed to AWS’s simple token service with action “GetCallerIdentity”

Return type requests.PreparedRequest

4.8 hvac.adapters

HTTP Client Library Adapters

`class hvac.adapters.Adapter(base_uri='http://localhost:8200', token=None, cert=None, verify=True, timeout=30, proxies=None, allow_redirects=True, session=None, namespace=None, ignore_exceptions=False)`

Bases: object

Abstract base class used when constructing adapters for use with the Client class.


```
__init__(base_uri='http://localhost:8200', token=None, cert=None, verify=True, timeout=30, proxies=None, allow_redirects=True, session=None, namespace=None, ignore_exceptions=False)
```

Create a new request adapter instance.

Parameters

- **base_uri** (*str*) – Base URL for the Vault instance being addressed.
- **token** (*str*) – Authentication token to include in requests sent to Vault.
- **cert** (*tuple*) – Certificates for use in requests sent to the Vault instance. This should be a tuple with the certificate and then key.
- **verify** (*Union[bool, str]*) – Either a boolean to indicate whether TLS verification should be performed when sending requests to Vault, or a string pointing at the CA bundle to use for verification. See <http://docs.python-requests.org/en/master/user/advanced/#ssl-cert-verification>.
- **timeout** (*int*) – The timeout value for requests sent to Vault.
- **proxies** (*dict*) – Proxies to use when performing requests. See: <http://docs.python-requests.org/en/master/user/advanced/#proxies>
- **allow_redirects** (*bool*) – Whether to follow redirects when sending requests to Vault.
- **session** (*request.Session*) – Optional session object to use when performing request.
- **namespace** (*str*) – Optional Vault Namespace.
- **ignore_exceptions** (*bool*) – If True, `_always_` return the response object for a given request. I.e., don't raise an exception based on response status code, etc.

```
auth(url, use_token=True, **kwargs)
```

Call to deprecated function 'auth'. This method will be removed in version '0.9.0' Please use the 'login' method on the

Docstring content from this method's replacement copied below: Perform a login request.

Associated request is typically to a path prefixed with "/v1/auth") and optionally stores the client token sent in the resulting Vault response for use by the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.

Parameters

- **url** (*str | unicode*) – Path to send the authentication request to.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the "token" attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the params sent with the request.

Returns The response of the auth request.

Return type requests.Response

```
close()
```

Close the underlying Requests session.

```
delete(url, **kwargs)
```

Performs a DELETE request.

Parameters

- **url** (*str* / *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type `requests.Response`

get (*url*, ***kwargs*)

Performs a GET request.

Parameters

- **url** (*str* / *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type `requests.Response`

get_login_token (*response*)

Extracts the client token from a login response.

Parameters **response** – The response object returned by the login method.

Returns A client token.

Return type `str`

head (*url*, ***kwargs*)

Performs a HEAD request.

Parameters

- **url** (*str* / *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type `requests.Response`

list (*url*, ***kwargs*)

Performs a LIST request.

Parameters

- **url** (*str* / *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type `requests.Response`

login (*url*, *use_token=True*, ***kwargs*)

Perform a login request.

Associated request is typically to a path prefixed with “/v1/auth”) and optionally stores the client token sent in the resulting Vault response for use by the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.

Parameters

- **url** (*str* | *unicode*) – Path to send the authentication request to.
- **use_token** (*bool*) – if True, uses the token in the response received from the auth request to set the “token” attribute on the the `hvac.adapters.Adapter()` instance under the `_adapater` Client attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the params sent with the request.

Returns The response of the auth request.

Return type requests.Response

post (*url*, ***kwargs*)

Performs a POST request.

Parameters

- **url** (*str* | *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type requests.Response

put (*url*, ***kwargs*)

Performs a PUT request.

Parameters

- **url** (*str* | *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type requests.Response

request (*method*, *url*, *headers=None*, *raise_exception=True*, ***kwargs*)

Main method for routing HTTP requests to the configured Vault `base_uri`. Intended to be implement by subclasses.

Parameters

- **method** (*str*) – HTTP method to use with the request. E.g., GET, POST, etc.
- **url** (*str* | *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance’s `base_uri` attribute.
- **headers** (*dict*) – Additional headers to include with the request.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.
- **raise_exception** (*bool*) – If True, raise an exception via `utils.raise_for_error()`. Set this parameter to False to bypass this functionality.

Returns The response of the request.

Return type requests.Response

static urljoin (**args*)

Joins given arguments into a url. Trailing and leading slashes are stripped for each argument.

Parameters `args` (*str* | *unicode*) – Multiple parts of a URL to be combined into one string.

Returns Full URL combining all provided arguments

Return type `str` | `unicode`

```
class hvac.adapters.JSONAdapter(base_uri='http://localhost:8200', token=None,
                                cert=None, verify=True, timeout=30, proxies=None, al-
                                low_redirects=True, session=None, namespace=None,
                                ignore_exceptions=False)
```

Bases: `hvac.adapters.RawAdapter`

The JSONAdapter adapter class. This adapter works just like the RawAdapter adapter except that HTTP 200 responses are returned as JSON dicts. All non-200 responses are returned as Response objects.

get_login_token (*response*)

Extracts the client token from a login response.

Parameters `response` (*dict* | `requests.Response`) – The response object returned by the login method.

Returns A client token.

Return type `str`

request (**args, **kwargs*)

Main method for routing HTTP requests to the configured Vault `base_uri`.

Parameters

- **args** (*list*) – Positional arguments to pass to RawAdapter.request.
- **kwargs** (*dict*) – Keyword arguments to pass to RawAdapter.request.

Returns Dict on HTTP 200 with JSON body, otherwise the response object.

Return type `dict` | `requests.Response`

```
class hvac.adapters.RawAdapter(base_uri='http://localhost:8200', token=None, cert=None, ver-
                                ify=True, timeout=30, proxies=None, allow_redirects=True,
                                session=None, namespace=None, ignore_exceptions=False)
```

Bases: `hvac.adapters.Adapter`

The RawAdapter adapter class. This adapter adds Vault-specific headers as required and optionally raises exceptions on errors, but always returns Response objects for requests.

get_login_token (*response*)

Extracts the client token from a login response.

Parameters `response` (`requests.Response`) – The response object returned by the login method.

Returns A client token.

Return type `str`

request (*method, url, headers=None, raise_exception=True, **kwargs*)

Main method for routing HTTP requests to the configured Vault `base_uri`.

Parameters

- **method** (*str*) – HTTP method to use with the request. E.g., GET, POST, etc.
- **url** (*str* | *unicode*) – Partial URL path to send the request to. This will be joined to the end of the instance's `base_uri` attribute.

- **headers** (*dict*) – Additional headers to include with the request.
- **raise_exception** (*bool*) – If True, raise an exception via `utils.raise_for_error()`. Set this parameter to False to bypass this functionality.
- **kwargs** (*dict*) – Additional keyword arguments to include in the requests call.

Returns The response of the request.

Return type `requests.Response`

`hvac.adapters.Request`
alias of `hvac.adapters.RawAdapter`

4.9 hvac.exceptions

exception `hvac.exceptions.BadGateway` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.Forbidden` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.InternalServerError` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.InvalidPath` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.InvalidRequest` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.ParamValidationError` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.RateLimitExceeded` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.Unauthorized` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.UnexpectedError` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.VaultDown` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

exception `hvac.exceptions.VaultError` (*message=None, errors=None*)

Bases: `Exception`

`__init__` (*message=None, errors=None*)

Initialize self. See `help(type(self))` for accurate signature.

exception `hvac.exceptions.VaultNotInitialized` (*message=None, errors=None*)

Bases: `hvac.exceptions.VaultError`

Feel free to open issues and/or pull requests with additional features or improvements! For general questions about contributing to hvac that don't fit in the scope of a GitHub issue, and for any folks are interested in becoming a maintainer of hvac, please feel free to join our gitter chat room for discussions at: gitter.im/hvac/community.

5.1 Typical Devevelopment Environment Setup

```
virtualenv hvac-env
source hvac-env/bin/activate

git clone https://github.com/hvac/hvac.git
cd hvac
pip install -e .
```

5.2 Testing

Integration tests will automatically start a Vault server in the background. Just make sure the latest `vault` binary is available in your `PATH`.

1. **Install Vault** or execute `tests/scripts/install-vault.sh`. Note: by default this script installs the OSS version of Vault. An enterprise trial version of the Vault binary is available for testing (but has an explicitly limited runtime). To run integration test cases requiring enterprise Vault, you can invoke the installation script with: `install-vault.sh <desired version> 'enterprise'`
2. Install requirements .. code-block:: guess

```
cd hvac pip install -r requirements.txt
```
3. Run tests: `make test`

5.3 Updating Requirements

This project uses `pip-tool`'s `pip-compile` utility to manage its various requirements. Any given requirements file can be manually updated by following the `pip-compile` comments at the top of the file. Alternatively, the `update-all-requirements` Makefile target can be used to update requirements across the board (this has a dependency on `docker` being available).

5.4 Documentation

5.4.1 Adding New Documentation Files

When adding documentation for an entirely new feature / class, it often makes sense to place the documentation in a new `.rst` file. After drafting the new file, be sure to add the file as an entry to at least one table of contents directive (e.g., `toctree`) to ensure it gets rendered and published on <https://hvac.readthedocs.io/>. As an example, the process for adding a new documentation file for a secrets engine related to Active Directory could involve:

1. Add a new file to `docs/usage/secrets_engines` with a name along the lines of `active_directory.rst`.
2. Update the `toctree` directive within `docs/usage/secrets_engines/index.rst` to add a line for `active_directory`.
3. Verify the new file is being included and rendered as expected by running `make html` from the `docs/` subdirectory. You can then view the rendered HTML documentation, in a browser or otherwise, by opening `docs/_build/html/index.html`.

5.4.2 Testing Docs

```
cd docs/  
pip install -r requirements.txt  
make doctest
```

5.4.3 Examples

Example code or general guides for methods in this module can be added under `docs/usage`. Any newly added or updated method in this module will ideally have a corresponding addition to these examples. New usage sections should also be added to the table of contents tracked in `docs/usage.rst`.

5.5 Backwards Compatibility Breaking Changes

Due to the close connection between this module and HashiCorp Vault versions, breaking changes are sometimes required. This can also occur as part of code refactoring to enable improvements in the module generally. In these cases:

- A deprecation notice should be displayed to callers of the module until the minor revision +2. E.g., a notice added in version 0.6.2 could see the marked method / functionality removed in version 0.8.0.
- Breaking changes should be called out in the `CHANGELOG.md` for the affected version.

5.6 Creating / Publishing Releases

- [] Checkout the `develop` branch: .. code-block:: guess
git checkout develop git pull
- [] Update the version number using `bumpversion`. Releases typically just use the “patch” `bumpversion` option; but “minor” and “major” are available as needed as needed. This will also add an appropriate git commit for the new version. .. code-block:: guess
bumpversion --no-tag {patch|minor|major}
- [] Pull up the current draft `hvac` release and use the `release-drafter` generated release body to update `CHANGELOG.md`. Then commit the changes: .. code-block:: guess
git commit CHANGELOG.md -m “Changelog updates for v\$(grep -oP ‘(?<=current_version =).*’
.bumpversion.cfg)”
- [] Git push the updated `develop` branch (`git push`) and open a PR to rebase merge the `develop` branch into `master`: <https://github.com/hvac/hvac/compare/master...develop>. Ensure the PR has the “release” label applied and then merge it.
- [] Publish the draft release on GitHub: <https://github.com/hvac/hvac/releases>. Ensure the tag is set to the release name (e.g., `vX.X.X`) and the target is the `master` branch. NOTE: `release-drafter` sets the release name by default. If performing a minor or major update, these values will need to be manually updated before publishing the draft release subsequently.

6.1 0.10.0 (February 26th, 2020)

6.1.1 Features

- Add a correct endpoint for CRL retrieving . GH-547

6.1.2 Documentation

- Fixes close quotes in example usage of `read_secret_version`. GH-557
- Fixes typo in docs: much -> must. GH-555

6.1.3 Miscellaneous

- Don't send optional parameters unless explicitly specified. GH-533

Note: GH-533 includes fundamental behavior involving sending parameters to API requests to Vault. Many hvac method parameters that would have been sent with default arguments no longer are included in requests to Vault. Notably, the following behavioral changes should be expected (copied from the related PR comments):

Azure:

- **CHANGED:** `create_role` parameter `policies` now accepts CSV string or list of strings

Database:

- **CHANGED:** `create_role` documentation updated to something meaningful

GCP:

- `configure` parameter `google_certs_endpoint` is deprecated
- `create_role` parameter `project_id` is deprecated by `bound_projects` (list)

GitHub:

- `configure` is missing a lot of parameters

LDAP:

- **CHANGED:** `configure` parameters `user_dn` and `group_dn` made optional
 - Retained argument position to prevent being a breaking change
- **CHANGED:** `hvac/constants/ldap.py` file removed as it is no longer used

MFA:

- This entire endpoint is deprecated so I didn't bother updating it

Okta:

- **CHANGED:** `configure` parameter `base_url` default value now differs from API documentation
 - This is likely just a [documentation issue](#)
- `register_user`, `read_user`, and `delete_user` duplicate URL parameter `username` in JSON payload
 - I left this one as-is as it doesn't appear to hurt anything
- Ditto for `delete_group`, but `register_group` and `list_group` correctly omit it

PKI:

- **CHANGED:** `sign_data` and `verify_signed_data` optional parameter `marshaling_algorithm` added

RADIUS:

- `configure` is missing a lot of parameters
- **BUG:** `register_user` attempted to convert `username` string into a CSV list (!) for POST data
 - Didn't hurt anything as `username` is extracted from URL path in Vault server
- **BUG:** `register_user` parameter `policies` never actually passed as parameter

System Backend:

- **Auth**
 - `enable_auth_method` parameter `plugin_name` is deprecated
 - **CHANGED:** `enable_audit_device` optional parameter `local` was added
- **Init**
 - `initialize` provides default for required API parameters `secret_shares` and `secret_threshold`
- **Key**
 - `start_root_token_generation` parameter `otp` is deprecated

Misc:

- There seems to be some discrepancy on how “extra arguments” are accepted:
 - Some methods use only `**kwargs` (e.g. `hvac/api/system_backend/auth.py`)
 - Some use `*args` and `**kwargs` (e.g. `hvac/api/secrets_engines/active_directory.py`)
 - `hvac/api/secrets_engines/pki.py` uses `extra_params={}`

- Most argument names match API parameter names, but some don't
 - Example: `hvac/api/auth_methods/ldap.py` configure uses `user_dn` instead of `userdn`
 - Example: `hvac/api/system_backend/auth.py` configure uses `method_type` instead of `type`
- Many methods duplicate URL parameters into JSON payload as well
 - This isn't necessary and fortunately Vault ignores the extra parameters
- `ttl`, `max_ttl`, `policies`, `period`, `num_uses` and a few other fields are deprecated as of Vault version 1.2.0
 - <https://github.com/hashicorp/vault/blob/master/CHANGELOG.md#120-july-30th-2019>

Thanks to @findmyname666, @llamasoft, @moisesguimaraes, @philherbert and Adrian Eib for their lovely contributions.

6.2 0.9.6 (November 20th, 2019)

6.2.1 Features

- Added userpass auth method. GH-519
- added rabbitmq secrets backend. GH-540
- Quote/Escape all URL placeholders. GH-532

6.2.2 Documentation

- Getting Started Guide and LDAP Auth Updates. GH-524

6.2.3 Miscellaneous

- Handle bad gateway from Vault. GH-542
- Fix GET/LIST typos. GH-536
- Fix Travis HEAD build + Overhaul install scripts. GH-535
- Improve Integration Test Error Handling. GH-531

Thanks to @DaveDeCaprio, @Dowwie, @drewmullen, @jeffwecan, @llamasoft and @vamshideveloper for their lovely contributions.

6.3 0.9.5 (July 19th, 2019)

6.3.1 Features

- Add Active Directory Secrets Engine Support. GH-508

6.3.2 Documentation

- Include Recently Added Namespace Documentation In Toctree. GH-509

Thanks to @jeffwecan and @vamshideveloper for their lovely contributions.

6.4 0.9.4 (July 18th, 2019)

6.4.1 Features

- Add delete_namespace Method and Establish Namespace Documentation. GH-500

6.4.2 Bug Fixes

- Fix consul configure_access/create_or_update_role Method Return Values. GH-502

6.4.3 Documentation

- Fix Database generate_credentials Docstring Params. GH-498

6.4.4 Miscellaneous

- Add config for updatedocs app. GH-495
- Add a Codeowners file for automatic reviewer assignments. GH-494

Thanks to @Tylerlhess, @drewmullen and @jeffwecan for their lovely contributions.

6.5 0.9.3 (July 7th, 2019)

6.5.1 Features

- Add Create and List Namespace System Backend Methods. GH-489
- Expanded Support for AWS Auth Method. GH-482
- Capabilities System Backend Support. GH-476

6.5.2 Bug Fixes

- GCP Auth Test Case Updates For Changes in Vault v1.1.1+. GH-487
- Change AWS generate_credentials request method to GET. GH-475

6.5.3 Documentation

- Numerous Fixes and Doctest Support for Transit Secrets Engine. GH-486

6.5.4 Miscellaneous

- Start Using Enterprise (Trial) Version of Vault For Travis CI Builds. [GH-478](#)
- Update Travis CI Test Matrix With Latest Vault Version & Drop Python 3.6. [GH-488](#)
- Set up release-drafter / *mostly* automated releases. [GH-485](#)

Thanks to @donjar, @fhemberger, @jeffwecan, @stevefranks and @stevenmanton for their lovely contributions.

6.6 0.9.2 (June 8th, 2019)

BUG FIXES:

- Fix kubernetes auth method list roles method. [GH-466](#)
- Enable consul secrets engine. [GH-460](#)
- Enable database secrets engine. [GH-455](#)
- Many fixes for the database secrets engine. [GH-457](#)

IMPROVEMENTS:

- The `enable_auth_method()`, `tune_auth_method()`, `enable_secrets_engine()`, `tune_mount_configuration()` system backend method now take arbitrary `**kwargs` parameters to provide greater support for variations in accepted parameters in the underlying Vault plugins.
- Azure auth params, add `num_uses`, change `bound_location` -> `bound_locations` and `bound_resource_group_names` -> `bound_resource_groups`. [GH-452](#)

MISCELLANEOUS:

- The hvac project now has gitter chat enabled. Feel free to check it out for any online discussions related to this module at: gitter.im/hvac/community! [GH-465](#)
- Added Vault agent socket listener usage example under the “advanced usage” documentation section at: hvac.readthedocs.io [GH-468](#)

Thanks to @denisvll, @Dudesons, and @drewmullen for their lovely contributions.

6.7 0.9.1 (May 25th, 2019)

BUG FIXES:

- Fix Azure list roles [GH-448](#)

IMPROVEMENTS:

- Support for the PKI secrets engine. [GH-436](#)

MISCELLANEOUS:

- `delete_roleaset()` method added to GCP secrets engine support. [GH-449](#)

Thanks to @nledez and @drewmullen for their lovely contributions.

6.8 0.9.0 (May 23rd, 2019)

BUG FIXES:

- Update path to `azure.login()` [GH-429](#)
- AWS secrets engine generate credentials updated to a post request. [GH-430](#)

IMPROVEMENTS:

- Support for the Radius auth method. [GH-420](#)
- Support for the Database secrets engine. [GH-431](#)
- Add the consul secret engine support [GH-432](#)
- Support for the GCP secrets engine. [GH-443](#)

MISCELLANEOUS:

- Remove logger call within adapters module [GH-445](#)
- Add docs for `auth_cubbyhole` [GH-427](#)

Thanks to @paulcaskey, @stevenmanton, @brad-alexander, @yoyomeng2, @JadeHayes, @Dudesons for their lovely contributions.

6.9 0.8.2 (April 4th, 2019)

BUG FIXES:

- Fix priority of client url and `VAULT_ADDR` environment variable. [GH-423](#)
- Update `setup.py` to only compile hvac package. [GH-418](#)

Thanks to @eltoder and @andytumelty for their lovely contributions.

6.10 0.8.1 (March 31st, 2019)

BUG FIXES:

- Fix `initialize()` method `recovery_shares` and `recovery_threshold` parameter validation regression. [GH-416](#)

6.11 0.8.0 (March 29th, 2019)

BACKWARDS COMPATIBILITY NOTICE:

- The `Client()` class constructor now behaves similarly to Vault CLI in that it uses the `VAULT_ADDR` environmental variable for the Client URL when that variable is set. Along the same lines, when no token is passed into the `Client()` constructor, it will attempt to load a token from the `VAULT_TOKEN` environmental variable or the `~/.vault-token` file where available. [GH-411](#)

IMPROVEMENTS:

- Support for the Kubernetes auth method. [GH-408](#)

BUG FIXES:

- Fix for comparison `recovery_threshold` and `recovery_shares` during initialization. [GH-398](#)
- Fix request method for AWS secrets engine `generate_credentials()` method. [GH-403](#)
- Fix request parameter (`n_bytes` -> `bytes`) for Transit secrets engine `generate_random_bytes()` method. [GH-377](#)

Thanks to @engstrom, @viralpoetry, @bootswithdefer, @steved, @kserrano, @spbsoluble, @uepoch, @singuliere, @frgaudet, @jsporna, & @mrsiesta for their lovely contributions.

6.12 0.7.2 (January 1st, 2019)

IMPROVEMENTS:

- Support for the AWS secrets engine. [GH-370](#)

BUG FIXES:

- Fixes for intermittent test case failures. [GH-361](#) & [GH-364](#)

MISCELLANEOUS:

- Travis CI builds now run against Python 3.7 (along side the previously tested 2.7 and 3.6 versions). [GH-360](#)
- Documentation build test case added. [GH-366](#)
- Module version now managed by the `bumpversion` utility exclusively. [GH-369](#)

6.13 0.7.1 (December 19th, 2018)

IMPROVEMENTS:

- Support for the Okta auth method. [GH-341](#)

BUG FIXES:

- Simplify redirect handling in `Adapter` class to fix issues following location headers with fully qualified URLs. Note: hvac now converts `//` to `/` within any paths. [GH-348](#)
- Fixed a bug where entity and group member IDs were not being passed in to Identity secrets engine group creation / updates. [GH-346](#)
- Ensure all types of responses for the `read_health_status()` system backend method can be retrieved without exceptions being raised. [GH-347](#)
- Fix `read_seal_status()` in `Client` class's `seal_status` property. [GH-354](#)

DOCUMENTATION UPDATES:

- Example GCP auth method `login()` call with `google-api-python-client` usage added: [Example with google-api-python-client Usage](#). [GH-350](#)

MISCELLANEOUS:

- Note: Starting after release 0.7.0, `develop` is the main integration branch for the hvac project. The `master` branch is now intended to capture the state of the most recent release.
- Test cases for hvac are no longer included in the release artifacts published to PyPi. [GH-334](#)
- The `create_or_update_policy` system backend method now supports a “pretty_print” argument for different JSON formatting. This allows create more viewable policy documents when retrieve existing policies (e.g., from within the Vault UI interface). [GH-342](#)

- Explicit support for Vault v0.8.3 dropped. CI/CD tests updated to run against Vault v1.0.0. [GH-344](#)

6.14 0.7.0 (November 1st, 2018)

DEPRECATION NOTICES:

- All auth method classes are now accessible under the `auth` property on the `hvac.Client` class. [GH-310](#). (E.g. the `github`, `ldap`, and `mfa` Client properties' methods are now accessible under `Client.auth.github`, etc.)
- All secrets engines classes are now accessible under the `secrets` property on the `hvac.Client` class. [GH-311](#) (E.g. the `kv`, Client property's methods are now accessible under `Client.secrets.kv`)
- All system backend classes are now accessible under the `sys` property on the `hvac.Client` class. [GH-314](#) ([[GH-314](#)] through [[GH-325](#)]) (E.g. methods such as `enable_secret_backend()` under the Client class are now accessible under `Client.sys.enable_secrets_engine()`, etc.)

IMPROVEMENTS:

- Support for Vault Namespaces. [GH-268](#)
- Support for the Identity secrets engine. [GH-269](#)
- Support for the GCP auth method. [GH-240](#)
- Support for the Azure auth method. [GH-286](#)
- Support for the Azure secrets engine. [GH-287](#)
- Expanded Transit secrets engine support. [GH-303](#)

Thanks to [@tiny-dancer](#), [@jacquat](#), [@deejay1](#), [@MJ111](#), [@jasonarewhy](#), and [@alexandernst](#) for their lovely contributions.

6.15 0.6.4 (September 5th, 2018)

IMPROVEMENTS:

- New KV secret engine-related classes added. See the [KV documentation](#) under `hvac's readthedocs.io` site for [usage / examples](#). [GH-257](#) / [GH-260](#)

MISCELLANEOUS:

- Language classifiers are now being included with the distribution. [GH-247](#)
- Token no longer being sent in URL path for the `Client.renew_token` method. [GH-250](#)
- Support for the response structure in newer versions of Vault within the `Client.get_policy` method. [GH-254](#)
- `config` and `plugin_name` parameters added to the `Client.enable_auth_backend` method. [GH-253](#)

Thanks to [@ijl](#), [@rastut](#), [@seuf](#), [@downeast](#) for their lovely contributions.

6.16 0.6.3 (August 8th, 2018)

DEPRECATION NOTICES:

- The `auth_github()` method within the `hvac.Client` class has been marked as deprecated and will be removed in hvac v0.8.0 (or later). Please update any callers of this method to use the `hvac.Client.github.login()` instead.
- The `auth_ldap()` method within the `hvac.Client` class has been marked as deprecated and will be removed in hvac v0.8.0 (or later). Please update any callers of this method to use the `hvac.Client.ldap.login()` instead.

IMPROVEMENTS:

- New Github auth method class added. See the [Github documentation for usage / examples](#). GH-242
- New Ldap auth method class added. See the [Ldap documentation for usage / examples](#). GH-244
- New Mfa auth method class added. See the [documentation for usage / examples](#). GH-255
- `auth_aws_iam()` method updated to include “region” parameter for deployments in different AWS regions. GH-243

DOCUMENTATION UPDATES:

- Additional guidance for how to configure hvac’s `Client` class to leverage self-signed certificates / private CA bundles has been added at: [Making Use of Private CA](#). GH-230
- Docstring for `verify Client` parameter corrected and expanded. GH-238

MISCELLANEOUS:

- Automated PyPi deploys via travis-ci removed. GH-226
- Repository transferred to the new “hvac” GitHub organization; thanks @ianunruh! GH-227
- Codecov (automatic code coverage reports) added. GH-229 / GH-228
- Tests subdirectory reorganized; now broken up by integration versus unit tests with subdirectories matching the module path for the code under test. GH-236

Thanks to @otakup0pe, @FabianFrank, @andrewheald for their lovely contributions.

6.17 0.6.2 (July 19th, 2018)

BACKWARDS COMPATIBILITY NOTICE:

- With the newly added `hvac.adapters.Request` class, request kwargs can no longer be directly modified via the `_kwargs` attribute on the `Client` class. If runtime modifications to this dictionary are required, callers either need to explicitly pass in a new `adapter` instance with the desired settings via the `adapter` property on the `Client` class *or* access the `_kwargs` property via the `adapter` property on the `Client` class.

See the [Advanced Usage](#) section of this module’s documentation for additional details.

IMPROVEMENTS:

- sphinx documentation and [readthedocs.io](#) project added. GH-222
- README.md included in setup tools metadata. GH-222
- All `tune_secret_backend()` parameters now accepted. GH-215
- Add `read_release()` method GH-218
- Added `adapter` module with `Request` class to abstract HTTP requests away from the `Client` class. GH-223

Thanks to @bbayszczak, @jvanbrunschot-coolblue for their lovely contributions.

6.18 0.6.1 (July 5th, 2018)

IMPROVEMENTS:

- Update `unwrap()` method to match current Vault versions [GH-149]
- Initial support for Kubernetes authentication backend [GH-210]
- Initial support for Google Cloud Platform (GCP) authentication backend [GH-206]
- Update `enable_secret_backend` function to support kv version 2 [GH-201]

BUG FIXES:

- Change URL parsing to allow for routes in the base Vault address (e.g., `https://example.com/vault`) [GH-212].

Thanks to @mracter, @cdsf, @SiN, @seanmalloy, for their lovely contributions.

6.19 0.6.0 (June 14, 2018)

BACKWARDS COMPATIBILITY NOTICE:

- Token revocation now sends the token in the request payload. Requires Vault >0.6.5
- Various methods have new and/or re-ordered keyword arguments. Code calling these methods with positional arguments may need to be modified.

IMPROVEMENTS:

- Ensure `mount_point` Parameter for All AWS EC2 Methods [GH-195]
- Add Methods for Auth Backend Tuning [GH-193]
- Customizable `approve_path / mount_point` [GH-190]
- Add more methods for the `userpass` backend [GH-175]
- Add `transit signature_algorithm` parameter [GH-174]
- Add `auth_iam_aws()` method [GH-170]
- `lookup_token` function POST token not GET [GH-164]
- `Create_role_secret_id` with `wrap_ttl` & fix `get_role_secret_id_accessor` [GH-159]
- Fixed `json()` from dict bug and added additional arguments on `auth_ec2()` method [GH-157]
- Support specifying period when creating EC2 roles [GH-140]
- Added support for `/sys/generate-root` endpoint [GH-131] / [GH-199]
- Added “`auth_cubbyhole`” method [GH-119]
- Send token/accessor as a payload to avoid being logged [GH-117]
- Add AppRole `delete_role` method [GH-112]

BUG FIXES:

- Always Specify `auth_type` In `create_ec2_role` [GH-197]
- Fix “double parsing” of JSON response in `auth_ec2` method [GH-181]

Thanks to @freimer, @ramiamar, @marcoslopes, @ianwestcott, @marc-sensenich, @sunghyun-lee, @jnaulty, @si-jis, @Myles-Steinhauser-Bose, @oxmane, @ltn, @bhannak, @tkinz27, @crmulliner, for their lovely contributions.

6.20 0.5.0 (February 20, 2018)

IMPROVEMENTS:

- Added `disallowed_policies` parameter to `create_token_role` method [GH-169]

Thanks to @morganda for their lovely contribution.

6.21 0.4.0 (February 1, 2018)

IMPROVEMENTS:

- Add support for the `period` parameter on token creation [GH-167]
- Add support for the `cidr_list` parameter for approle secrets [GH-114]

BUG FIXES:

- Documentation is now more accurate [GH-165] / [GH-154]

Thanks to @ti-mo, @dhoeric, @RAbraham, @lhdumittan, @ahsanali for their lovely contributions.

6.22 0.3.0 (November 9, 2017)

This is just the highlights, there have been a bunch of changes!

IMPROVEMENTS:

- Some AppRole support [GH-77]
- Response Wrapping [GH-85]
- AWS EC2 stuff [GH-107], [GH-109]

BUG FIXES

- Better handling of various error states [GH-79], [GH-125]

Thanks to @ianwestcott, @s3u, @mracter, @intgr, @jkdihenkar, @gaell, @henriquegemignani, @bfeeser, @nicr9, @mwielgoszewski, @mtougeron for their contributions!

6.23 0.2.17 (December 15, 2016)

IMPROVEMENTS:

- Add token role support [GH-94]
- Add support for Python 2.6 [GH-92]
- Allow setting the `explicit_max_ttl` when creating a token [GH-81]
- Add support for write response wrapping [GH-85]

BUG FIXES:

- Fix app role endpoints for newer versions of Vault [GH-93]

6.24 0.2.16 (September 12, 2016)

Thanks to @otakup0pe, @nicr9, @marcoslopes, @caiotomazelli, and @blarghmatey for their contributions!

IMPROVEMENTS:

- Add EC2 auth support [GH-61]
- Add support for token accessors [GH-69]
- Add support for response wrapping [GH-70]
- Add AppRole auth support [GH-77]

BUG FIXES:

- Fix `no_default_policy` parameter in `create_token` [GH-65]
- Fix EC2 auth double JSON parsing [GH-76]

6.25 0.2.15 (June 22nd, 2016)

Thanks to @blarghmatey, @stevenmanton, and @ahline for their contributions!

IMPROVEMENTS:

- Add methods for manipulating app/user IDs [GH-62]
- Add ability to automatically parse policies with `pyhcl` [GH-58]
- Add TTL option to `create_userpass` [GH-60]
- Add support for backing up keys on rekey [GH-57]
- Handle non-JSON error responses correctly [GH-46]

BUG FIXES:

- `is_authenticated` now handles new error type for Vault 0.6.0

6.26 0.2.14 (June 2nd, 2016)

BUG FIXES:

- Fix improper URL being used when leader redirection occurs [GH-56]

6.27 0.2.13 (May 31st, 2016)

IMPROVEMENTS:

- Add support for Requests sessions [GH-53]

BUG FIXES:

- Properly handle redirects from Vault server [GH-51]

6.28 0.2.12 (May 12th, 2016)

IMPROVEMENTS:

- Add support for `increment` in renewal of secret [GH-48]

BUG FIXES:

- Use unicode literals when constructing URLs [GH-50]

6.29 0.2.10 (April 8th, 2016)

IMPROVEMENTS:

- Add support for list operation [GH-47]

6.30 0.2.9 (March 18th, 2016)

IMPROVEMENTS:

- Add support for nonce during rekey operation [GH-42]
- Add get method for policies [GH-43]
- Add delete method for userpass auth backend [GH-45]
- Add support for response to rekey init

6.31 0.2.8 (February 2nd, 2016)

IMPROVEMENTS:

- Convenience methods for managing userpass and app-id entries
- Support for new API changes in Vault v0.4.0

6.32 0.2.7 (December 16th, 2015)

IMPROVEMENTS:

- Add support for PGP keys when rekeying [GH-28]

BUG FIXES:

- Fixed token metadata parameter [GH-27]

6.33 0.2.6 (October 30th, 2015)

IMPROVEMENTS:

- Add support for `revoke-self`
- Restrict `requests` dependency to modern version

6.34 0.2.5 (September 29th, 2015)

IMPROVEMENTS:

- Add support for API changes/additions in Vault v0.3.0
 - Tunable config on secret backends
 - MFA on username/password and LDAP auth backends
 - PGP encryption for unseal keys

6.35 0.2.4 (July 23rd, 2015)

BUG FIXES:

- Fix write response handling [GH-19]

6.36 0.2.3 (July 18th, 2015)

BUG FIXES

- Fix error handling for next Vault release

IMPROVEMENTS:

- Add support for rekey/rotate APIs

6.37 0.2.2 (June 12th, 2015)

BUG FIXES:

- Restrict `requests` dependency to 2.5.0 or later

IMPROVEMENTS:

- Return latest seal status from `unseal_multi`

6.38 0.2.1 (June 3rd, 2015)

BUG FIXES:

- Use arguments passed to `initialize` method

6.39 0.2.0 (May 25th, 2015)

BACKWARDS COMPATIBILITY NOTICE:

- Requires Vault 0.1.2 or later for `X-Vault-Token` header
- `auth_token` method removed in favor of `token` property

- `read` method no longer raises `hvac.exceptions.InvalidPath` on nonexistent paths

IMPROVEMENTS:

- Tolerate falsey URL in client constructor
- Add ability to auth without changing to new token
- Add `is_authenticated` convenience method
- Return `None` when reading nonexistent path

6.40 0.1.1 (May 20th, 2015)

IMPROVEMENTS:

- Add `is_sealed` convenience method
- Add `unseal_multi` convenience method

BUG FIXES:

- Remove `secret_shares` argument from `unseal` method

6.41 0.1.0 (May 17th, 2015)

- Initial release

CHAPTER 7

Indices and tables

- `genindex`
- `modindex`
- `search`

Source code repository hosted at github.com/hvac/hvac.

h

`hvac.adapters`, 266
`hvac.api`, 166
`hvac.api.auth_methods`, 168
`hvac.api.secrets_engines`, 200
`hvac.api.system_backend`, 247
`hvac.aws_utils`, 266
`hvac.exceptions`, 271
`hvac.utils`, 263
`hvac.v1`, 123

Symbols

__init__() (*hvac.adapters.Adapter method*), 266
 __init__() (*hvac.api.SystemBackend method*), 167
 __init__() (*hvac.api.VaultApiBase method*), 167
 __init__() (*hvac.api.VaultApiCategory method*), 167
 __init__() (*hvac.api.secrets_engines.Kv method*), 220
 __init__() (*hvac.api.system_backend.SystemBackend method*), 263
 __init__() (*hvac.aws_utils.SigV4Auth method*), 266
 __init__() (*hvac.exceptions.VaultError method*), 271
 __init__() (*hvac.v1.Client method*), 123

A

ActiveDirectory (*class in hvac.api.secrets_engines*), 209
 Adapter (*class in hvac.adapters*), 266
 adapter (*hvac.api.VaultApiCategory attribute*), 167
 adapter (*hvac.v1.Client attribute*), 124
 add_auth() (*hvac.aws_utils.SigV4Auth method*), 266
 allow_redirects (*hvac.v1.Client attribute*), 124
 allowed_kv_versions (*hvac.api.secrets_engines.Kv attribute*), 220
 Audit (*class in hvac.api.system_backend*), 247
 audit_hash() (*hvac.v1.Client method*), 124
 Auth (*class in hvac.api.system_backend*), 248
 auth (*hvac.v1.Client attribute*), 124
 auth() (*hvac.adapters.Adapter method*), 267
 auth_app_id() (*hvac.v1.Client method*), 124
 auth_approle() (*hvac.v1.Client method*), 124
 auth_aws_iam() (*hvac.v1.Client method*), 125
 auth_cubbyhole() (*hvac.v1.Client method*), 125
 auth_ec2() (*hvac.v1.Client method*), 125
 auth_gcp() (*hvac.v1.Client method*), 125
 auth_github() (*hvac.v1.Client method*), 126
 auth_kubernetes() (*hvac.v1.Client method*), 126
 auth_ldap() (*hvac.v1.Client method*), 126
 auth_tls() (*hvac.v1.Client method*), 127
 auth_userpass() (*hvac.v1.Client method*), 127

AuthMethods (*class in hvac.api*), 166
 AuthMethods (*class in hvac.api.auth_methods*), 168
 Aws (*class in hvac.api.auth_methods*), 192
 Aws (*class in hvac.api.secrets_engines*), 200
 Azure (*class in hvac.api.auth_methods*), 168
 Azure (*class in hvac.api.secrets_engines*), 204

B

backup_key() (*hvac.api.secrets_engines.Transit method*), 234
 BadGateway, 271

C

calculate_hash() (*hvac.api.system_backend.Audit method*), 247
 cancel_generate_root() (*hvac.v1.Client method*), 127
 cancel_rekey() (*hvac.api.system_backend.Key method*), 252
 cancel_rekey() (*hvac.v1.Client method*), 127
 cancel_root_generation() (*hvac.api.system_backend.Key method*), 253
 Capabilities (*class in hvac.api.system_backend*), 250
 Client (*class in hvac.v1*), 123
 close() (*hvac.adapters.Adapter method*), 267
 close() (*hvac.v1.Client method*), 128
 comma_delimited_to_list() (*in module hvac.utils*), 263
 configure() (*hvac.api.auth_methods.Aws method*), 192
 configure() (*hvac.api.auth_methods.Azure method*), 168
 configure() (*hvac.api.auth_methods.Gcp method*), 171
 configure() (*hvac.api.auth_methods.Github method*), 175
 configure() (*hvac.api.auth_methods.Kubernetes method*), 177

[configure\(\)](#) (*hvac.api.auth_methods.Ldap method*), 180
[configure\(\)](#) (*hvac.api.auth_methods.Mfa method*), 185
[configure\(\)](#) (*hvac.api.auth_methods.Okta method*), 187
[configure\(\)](#) (*hvac.api.auth_methods.Radius method*), 190
[configure\(\)](#) (*hvac.api.secrets_engines.ActiveDirectory method*), 209
[configure\(\)](#) (*hvac.api.secrets_engines.Azure method*), 204
[configure\(\)](#) (*hvac.api.secrets_engines.Database method*), 243
[configure\(\)](#) (*hvac.api.secrets_engines.Gcp method*), 206
[configure\(\)](#) (*hvac.api.secrets_engines.KvV2 method*), 222
[configure\(\)](#) (*hvac.api.secrets_engines.RabbitMQ method*), 245
[configure_duo_access\(\)](#) (*hvac.api.auth_methods.Mfa method*), 185
[configure_duo_behavior\(\)](#) (*hvac.api.auth_methods.Mfa method*), 186
[configure_identity_integration\(\)](#) (*hvac.api.auth_methods.Aws method*), 193
[configure_identity_whitelist_tidy\(\)](#) (*hvac.api.auth_methods.Aws method*), 193
[configure_lease\(\)](#) (*hvac.api.secrets_engines.Aws method*), 200
[configure_lease\(\)](#) (*hvac.api.secrets_engines.RabbitMQ method*), 246
[configure_role_tag_blacklist_tidy\(\)](#) (*hvac.api.auth_methods.Aws method*), 193
[configure_root_iam_credentials\(\)](#) (*hvac.api.secrets_engines.Aws method*), 200
[create_app_id\(\)](#) (*hvac.v1.Client method*), 128
[create_certificate_configuration\(\)](#) (*hvac.api.auth_methods.Aws method*), 193
[create_ec2_role\(\)](#) (*hvac.v1.Client method*), 128
[create_ec2_role_tag\(\)](#) (*hvac.v1.Client method*), 129
[create_key\(\)](#) (*hvac.api.secrets_engines.Transit method*), 234
[create_kubernetes_configuration\(\)](#) (*hvac.v1.Client method*), 130
[create_kubernetes_role\(\)](#) (*hvac.v1.Client method*), 130
[create_namespace\(\)](#) (*hvac.api.system_backend.Namespace method*), 260
[create_or_update_entity\(\)](#) (*hvac.api.secrets_engines.Identity method*), 210
[create_or_update_entity_alias\(\)](#) (*hvac.api.secrets_engines.Identity method*), 211
[create_or_update_entity_by_name\(\)](#) (*hvac.api.secrets_engines.Identity method*), 211
[create_or_update_group\(\)](#) (*hvac.api.auth_methods.Ldap method*), 181
[create_or_update_group\(\)](#) (*hvac.api.secrets_engines.Identity method*), 211
[create_or_update_group_alias\(\)](#) (*hvac.api.secrets_engines.Identity method*), 212
[create_or_update_group_by_name\(\)](#) (*hvac.api.secrets_engines.Identity method*), 212
[create_or_update_policy\(\)](#) (*hvac.api.system_backend.Policy method*), 261
[create_or_update_role\(\)](#) (*hvac.api.secrets_engines.ActiveDirectory method*), 209
[create_or_update_role\(\)](#) (*hvac.api.secrets_engines.Aws method*), 201
[create_or_update_role\(\)](#) (*hvac.api.secrets_engines.Azure method*), 204
[create_or_update_role\(\)](#) (*hvac.api.secrets_engines.Pki method*), 226
[create_or_update_roleset\(\)](#) (*hvac.api.secrets_engines.Gcp method*), 206
[create_or_update_secret\(\)](#) (*hvac.api.secrets_engines.KvV1 method*), 221
[create_or_update_secret\(\)](#) (*hvac.api.secrets_engines.KvV2 method*), 223
[create_or_update_user\(\)](#) (*hvac.api.auth_methods.Ldap method*), 181
[create_or_update_user\(\)](#) (*hvac.api.auth_methods.Userpass method*), 183
[create_role\(\)](#) (*hvac.api.auth_methods.Aws method*), 194
[create_role\(\)](#) (*hvac.api.auth_methods.Azure method*), 169
[create_role\(\)](#) (*hvac.api.auth_methods.Gcp method*), 172
[create_role\(\)](#) (*hvac.api.auth_methods.Kubernetes*

- method), 178
- create_role() (hvac.api.secrets_engines.Database method), 244
- create_role() (hvac.api.secrets_engines.RabbitMQ method), 246
- create_role() (hvac.v1.Client method), 131
- create_role_custom_secret_id() (hvac.v1.Client method), 131
- create_role_secret_id() (hvac.v1.Client method), 131
- create_role_tags() (hvac.api.auth_methods.Aws method), 195
- create_sts_role() (hvac.api.auth_methods.Aws method), 195
- create_token() (hvac.v1.Client method), 131
- create_token_role() (hvac.v1.Client method), 132
- create_user_id() (hvac.v1.Client method), 133
- create_userpass() (hvac.v1.Client method), 133
- create_vault_ec2_certificate_configuration() (hvac.v1.Client method), 133
- create_vault_ec2_client_configuration() (hvac.v1.Client method), 134
- ## D
- Database (class in hvac.api.secrets_engines), 243
- decrypt_data() (hvac.api.secrets_engines.Transit method), 235
- default_kv_version (hvac.api.secrets_engines.Kv attribute), 220
- delete() (hvac.adapters.Adapter method), 267
- delete() (hvac.v1.Client method), 135
- delete_app_id() (hvac.v1.Client method), 135
- delete_blacklist_tags() (hvac.api.auth_methods.Aws method), 196
- delete_certificate_configuration() (hvac.api.auth_methods.Aws method), 196
- delete_config() (hvac.api.auth_methods.Aws method), 196
- delete_config() (hvac.api.auth_methods.Azure method), 169
- delete_config() (hvac.api.auth_methods.Gcp method), 173
- delete_config() (hvac.api.secrets_engines.Azure method), 205
- delete_connection() (hvac.api.secrets_engines.Database method), 244
- delete_ec2_role() (hvac.v1.Client method), 135
- delete_entity() (hvac.api.secrets_engines.Identity method), 213
- delete_entity_alias() (hvac.api.secrets_engines.Identity method), 213
- delete_entity_by_name() (hvac.api.secrets_engines.Identity method), 213
- delete_group() (hvac.api.auth_methods.Ldap method), 182
- delete_group() (hvac.api.auth_methods.Okta method), 187
- delete_group() (hvac.api.secrets_engines.Identity method), 214
- delete_group_alias() (hvac.api.secrets_engines.Identity method), 214
- delete_group_by_name() (hvac.api.secrets_engines.Identity method), 214
- delete_identity_whitelist_entries() (hvac.api.auth_methods.Aws method), 196
- delete_identity_whitelist_tidy() (hvac.api.auth_methods.Aws method), 197
- delete_key() (hvac.api.secrets_engines.Transit method), 235
- delete_kubernetes_role() (hvac.v1.Client method), 135
- delete_latest_version_of_secret() (hvac.api.secrets_engines.KvV2 method), 223
- delete_metadata_and_all_versions() (hvac.api.secrets_engines.KvV2 method), 223
- delete_namespace() (hvac.api.system_backend.Namespace method), 260
- delete_policy() (hvac.api.system_backend.Policy method), 261
- delete_policy() (hvac.v1.Client method), 135
- delete_role() (hvac.api.auth_methods.Aws method), 197
- delete_role() (hvac.api.auth_methods.Azure method), 170
- delete_role() (hvac.api.auth_methods.Gcp method), 173
- delete_role() (hvac.api.auth_methods.Kubernetes method), 178
- delete_role() (hvac.api.secrets_engines.ActiveDirectory method), 210
- delete_role() (hvac.api.secrets_engines.Aws method), 202
- delete_role() (hvac.api.secrets_engines.Database method), 244
- delete_role() (hvac.api.secrets_engines.Pki method), 227
- delete_role() (hvac.api.secrets_engines.RabbitMQ method), 246
- delete_role() (hvac.v1.Client method), 135
- delete_role_secret_id() (hvac.v1.Client

method), 136
delete_role_secret_id_accessor() (hvac.v1.Client method), 136
delete_role_tag_blacklist_tidy() (hvac.api.auth_methods.Aws method), 197
delete_roleset() (hvac.api.secrets_engines.Gcp method), 207
delete_root() (hvac.api.secrets_engines.Pki method), 227
delete_secret() (hvac.api.secrets_engines.KvV1 method), 221
delete_secret_versions() (hvac.api.secrets_engines.KvV2 method), 224
delete_sts_role() (hvac.api.auth_methods.Aws method), 197
delete_token_role() (hvac.v1.Client method), 136
delete_user() (hvac.api.auth_methods.Ldap method), 182
delete_user() (hvac.api.auth_methods.Okta method), 187
delete_user() (hvac.api.auth_methods.Radius method), 190
delete_user() (hvac.api.auth_methods.Userpass method), 184
delete_user_id() (hvac.v1.Client method), 136
delete_userpass() (hvac.v1.Client method), 136
delete_vault_ec2_client_configuration() (hvac.v1.Client method), 137
deprecated_method() (in module hvac.utils), 263
destroy_secret_versions() (hvac.api.secrets_engines.KvV2 method), 224
disable_audit_backend() (hvac.v1.Client method), 137
disable_audit_device() (hvac.api.system_backend.Audit method), 247
disable_auth_backend() (hvac.v1.Client method), 137
disable_auth_method() (hvac.api.system_backend.Auth method), 248
disable_secret_backend() (hvac.v1.Client method), 137
disable_secrets_engine() (hvac.api.system_backend.Mount method), 257

E

ec2_login() (hvac.api.auth_methods.Aws method), 197

edit_labels_on_gce_role() (hvac.api.auth_methods.Gcp method), 173
edit_service_accounts_on_iam_role() (hvac.api.auth_methods.Gcp method), 174
enable_audit_backend() (hvac.v1.Client method), 138
enable_audit_device() (hvac.api.system_backend.Audit method), 248
enable_auth_backend() (hvac.v1.Client method), 138
enable_auth_method() (hvac.api.system_backend.Auth method), 248
enable_secret_backend() (hvac.v1.Client method), 139
enable_secrets_engine() (hvac.api.system_backend.Mount method), 258
encrypt_data() (hvac.api.secrets_engines.Transit method), 235
export_key() (hvac.api.secrets_engines.Transit method), 236

F

Forbidden, 271
format_url() (in module hvac.utils), 264

G

Gcp (class in hvac.api.auth_methods), 171
Gcp (class in hvac.api.secrets_engines), 206
generate_certificate() (hvac.api.secrets_engines.Pki method), 227
generate_credentials() (hvac.api.secrets_engines.Aws method), 202
generate_credentials() (hvac.api.secrets_engines.Azure method), 205
generate_credentials() (hvac.api.secrets_engines.Database method), 244
generate_credentials() (hvac.api.secrets_engines.RabbitMQ method), 247
generate_data_key() (hvac.api.secrets_engines.Transit method), 237
generate_hmac() (hvac.api.secrets_engines.Transit method), 237
generate_intermediate() (hvac.api.secrets_engines.Pki method), 228
generate_method_deprecation_message() (in module hvac.utils), 264

`generate_oauth2_access_token()` (*hvac.api.secrets_engines.Gcp method*), 207
`generate_property_deprecation_message()` (*in module hvac.utils*), 264
`generate_random_bytes()` (*hvac.api.secrets_engines.Transit method*), 238
`generate_root()` (*hvac.api.secrets_engines.Pki method*), 228
`generate_root()` (*hvac.api.system_backend.Key method*), 253
`generate_root()` (*hvac.v1.Client method*), 140
`generate_root_status` (*hvac.v1.Client attribute*), 140
`generate_service_account_key()` (*hvac.api.secrets_engines.Gcp method*), 207
`generate_sigv4_auth_request()` (*in module hvac.aws_utils*), 266
`get()` (*hvac.adapters.Adapter method*), 268
`get_app_id()` (*hvac.v1.Client method*), 140
`get_auth_backend_tuning()` (*hvac.v1.Client method*), 140
`get_backed_up_keys()` (*hvac.v1.Client method*), 141
`get_capabilities()` (*hvac.api.system_backend.Capabilities method*), 250
`get_ec2_role()` (*hvac.v1.Client method*), 141
`get_encryption_key_status()` (*hvac.api.system_backend.Key method*), 253
`get_kubernetes_configuration()` (*hvac.v1.Client method*), 141
`get_kubernetes_role()` (*hvac.v1.Client method*), 141
`get_login_token()` (*hvac.adapters.Adapter method*), 268
`get_login_token()` (*hvac.adapters.JSONAdapter method*), 270
`get_login_token()` (*hvac.adapters.RawAdapter method*), 270
`get_policy()` (*hvac.v1.Client method*), 142
`get_private_attr_name()` (*hvac.api.VaultApiCategory static method*), 167
`get_role()` (*hvac.v1.Client method*), 142
`get_role_id()` (*hvac.v1.Client method*), 142
`get_role_secret_id()` (*hvac.v1.Client method*), 142
`get_role_secret_id_accessor()` (*hvac.v1.Client method*), 142
`get_secret_backend_tuning()` (*hvac.v1.Client method*), 142
`get_token_from_env()` (*in module hvac.utils*), 265
`get_user_id()` (*hvac.v1.Client method*), 143
`get_vault_ec2_certificate_configuration()` (*hvac.v1.Client method*), 143
`get_vault_ec2_client_configuration()` (*hvac.v1.Client method*), 143
`getattr_with_deprecated_properties()` (*in module hvac.utils*), 265
Github (*class in hvac.api.auth_methods*), 175

H

`ha_status` (*hvac.v1.Client attribute*), 144
`hash_data()` (*hvac.api.secrets_engines.Transit method*), 238
`head()` (*hvac.adapters.Adapter method*), 268
Health (*class in hvac.api.system_backend*), 251
hvac.adapters (*module*), 266
hvac.api (*module*), 166
hvac.api.auth_methods (*module*), 168
hvac.api.secrets_engines (*module*), 200
hvac.api.system_backend (*module*), 247
hvac.aws_utils (*module*), 266
hvac.exceptions (*module*), 271
hvac.utils (*module*), 263
hvac.v1 (*module*), 123

I

`iam_login()` (*hvac.api.auth_methods.Aws method*), 197
Identity (*class in hvac.api.secrets_engines*), 210
implemented_classes (*hvac.api.auth_methods.AuthMethods attribute*), 168
implemented_classes (*hvac.api.AuthMethods attribute*), 166
implemented_classes (*hvac.api.secrets_engines.SecretsEngines attribute*), 243
implemented_classes (*hvac.api.SecretsEngines attribute*), 167
implemented_classes (*hvac.api.system_backend.SystemBackend attribute*), 263
implemented_classes (*hvac.api.SystemBackend attribute*), 167
implemented_classes (*hvac.api.VaultApiCategory attribute*), 168
Init (*class in hvac.api.system_backend*), 251
`initialize()` (*hvac.api.system_backend.Init method*), 251
`initialize()` (*hvac.v1.Client method*), 144
InternalServerError, 271
InvalidPath, 271

- InvalidRequest, 271
- is_authenticated() (*hvac.v1.Client method*), 144
- is_initialized() (*hvac.api.system_backend.Init method*), 252
- is_initialized() (*hvac.v1.Client method*), 144
- is_sealed() (*hvac.api.system_backend.Seal method*), 261
- is_sealed() (*hvac.v1.Client method*), 145
- J**
- JSONAdapter (*class in hvac.adapters*), 270
- K**
- Key (*class in hvac.api.system_backend*), 252
- key_status (*hvac.v1.Client attribute*), 145
- Kubernetes (*class in hvac.api.auth_methods*), 177
- Kv (*class in hvac.api.secrets_engines*), 220
- KvV1 (*class in hvac.api.secrets_engines*), 221
- KvV2 (*class in hvac.api.secrets_engines*), 222
- L**
- Ldap (*class in hvac.api.auth_methods*), 180
- Leader (*class in hvac.api.system_backend*), 256
- Lease (*class in hvac.api.system_backend*), 256
- list() (*hvac.adapters.Adapter method*), 268
- list() (*hvac.v1.Client method*), 145
- list_audit_backends() (*hvac.v1.Client method*), 145
- list_auth_backends() (*hvac.v1.Client method*), 145
- list_auth_methods() (*hvac.api.system_backend.Auth method*), 249
- list_blacklist_tags() (*hvac.api.auth_methods.Aws method*), 197
- list_certificate_configurations() (*hvac.api.auth_methods.Aws method*), 197
- list_certificates() (*hvac.api.secrets_engines.Pki method*), 228
- list_connections() (*hvac.api.secrets_engines.Database method*), 245
- list_ec2_roles() (*hvac.v1.Client method*), 145
- list_enabled_audit_devices() (*hvac.api.system_backend.Audit method*), 248
- list_entities() (*hvac.api.secrets_engines.Identity method*), 214
- list_entities_by_name() (*hvac.api.secrets_engines.Identity method*), 214
- list_entity_aliases() (*hvac.api.secrets_engines.Identity method*), 215
- list_group_aliases() (*hvac.api.secrets_engines.Identity method*), 215
- list_groups() (*hvac.api.auth_methods.Ldap method*), 182
- list_groups() (*hvac.api.auth_methods.Okta method*), 188
- list_groups() (*hvac.api.secrets_engines.Identity method*), 215
- list_groups_by_name() (*hvac.api.secrets_engines.Identity method*), 215
- list_identity_whitelist() (*hvac.api.auth_methods.Aws method*), 198
- list_keys() (*hvac.api.secrets_engines.Transit method*), 239
- list_kubernetes_roles() (*hvac.v1.Client method*), 146
- list_leases() (*hvac.api.system_backend.Lease method*), 256
- list_mounted_secrets_engines() (*hvac.api.system_backend.Mount method*), 259
- list_namespaces() (*hvac.api.system_backend.Namespace method*), 260
- list_policies() (*hvac.api.system_backend.Policy method*), 261
- list_policies() (*hvac.v1.Client method*), 146
- list_role_secrets() (*hvac.v1.Client method*), 146
- list_roles() (*hvac.api.auth_methods.Aws method*), 198
- list_roles() (*hvac.api.auth_methods.Azure method*), 170
- list_roles() (*hvac.api.auth_methods.Gcp method*), 174
- list_roles() (*hvac.api.auth_methods.Kubernetes method*), 179
- list_roles() (*hvac.api.secrets_engines.ActiveDirectory method*), 210
- list_roles() (*hvac.api.secrets_engines.Aws method*), 203
- list_roles() (*hvac.api.secrets_engines.Azure method*), 205
- list_roles() (*hvac.api.secrets_engines.Database method*), 245
- list_roles() (*hvac.api.secrets_engines.Pki method*), 228
- list_roles() (*hvac.v1.Client method*), 146
- list_rolesets() (*hvac.api.secrets_engines.Gcp method*), 208
- list_secret_backends() (*hvac.v1.Client method*), 146

- list_secrets() (*hvac.api.secrets_engines.KvV1 method*), 222
- list_secrets() (*hvac.api.secrets_engines.KvV2 method*), 224
- list_sts_roles() (*hvac.api.auth_methods.Aws method*), 198
- list_to_comma_delimited() (*in module hvac.utils*), 265
- list_token_roles() (*hvac.v1.Client method*), 146
- list_user() (*hvac.api.auth_methods.Userpass method*), 184
- list_userpass() (*hvac.v1.Client method*), 147
- list_users() (*hvac.api.auth_methods.Ldap method*), 182
- list_users() (*hvac.api.auth_methods.Okta method*), 188
- list_users() (*hvac.api.auth_methods.Radius method*), 190
- list_vault_ec2_certificate_configurations() (*hvac.v1.Client method*), 147
- login() (*hvac.adapters.Adapter method*), 268
- login() (*hvac.api.auth_methods.Azure method*), 170
- login() (*hvac.api.auth_methods.Gcp method*), 174
- login() (*hvac.api.auth_methods.Github method*), 175
- login() (*hvac.api.auth_methods.Kubernetes method*), 179
- login() (*hvac.api.auth_methods.Ldap method*), 182
- login() (*hvac.api.auth_methods.Okta method*), 188
- login() (*hvac.api.auth_methods.Radius method*), 190
- login() (*hvac.api.auth_methods.Userpass method*), 184
- login() (*hvac.v1.Client method*), 147
- logout() (*hvac.v1.Client method*), 147
- lookup_entity() (*hvac.api.secrets_engines.Identity method*), 216
- lookup_group() (*hvac.api.secrets_engines.Identity method*), 216
- lookup_token() (*hvac.v1.Client method*), 147
- ## M
- map_team() (*hvac.api.auth_methods.Github method*), 176
- map_user() (*hvac.api.auth_methods.Github method*), 176
- merge_entities() (*hvac.api.secrets_engines.Identity method*), 216
- Mfa (*class in hvac.api.auth_methods*), 185
- Mount (*class in hvac.api.system_backend*), 257
- move_backend() (*hvac.api.system_backend.Mount method*), 259
- ## N
- Namespace (*class in hvac.api.system_backend*), 260
- ## O
- Okta (*class in hvac.api.auth_methods*), 186
- ## P
- ParamValidationError, 271
- patch() (*hvac.api.secrets_engines.KvV2 method*), 225
- Pki (*class in hvac.api.secrets_engines*), 226
- place_role_tags_in_blacklist() (*hvac.api.auth_methods.Aws method*), 198
- Policy (*class in hvac.api.system_backend*), 260
- post() (*hvac.adapters.Adapter method*), 269
- put() (*hvac.adapters.Adapter method*), 269
- ## R
- RabbitMQ (*class in hvac.api.secrets_engines*), 245
- Radius (*class in hvac.api.auth_methods*), 190
- raise_for_error() (*in module hvac.utils*), 265
- RateLimitExceeded, 271
- RawAdapter (*class in hvac.adapters*), 270
- read() (*hvac.v1.Client method*), 148
- read_auth_method_tuning() (*hvac.api.system_backend.Auth method*), 249
- read_backup_keys() (*hvac.api.system_backend.Key method*), 253
- read_ca_certificate() (*hvac.api.secrets_engines.Pki method*), 229
- read_ca_certificate_chain() (*hvac.api.secrets_engines.Pki method*), 229
- read_certificate() (*hvac.api.secrets_engines.Pki method*), 229
- read_certificate_configuration() (*hvac.api.auth_methods.Aws method*), 198
- read_config() (*hvac.api.auth_methods.Aws method*), 198
- read_config() (*hvac.api.auth_methods.Azure method*), 171
- read_config() (*hvac.api.auth_methods.Gcp method*), 175
- read_config() (*hvac.api.auth_methods.Kubernetes method*), 179
- read_config() (*hvac.api.auth_methods.Okta method*), 188
- read_config() (*hvac.api.secrets_engines.ActiveDirectory method*), 210
- read_config() (*hvac.api.secrets_engines.Azure method*), 205
- read_config() (*hvac.api.secrets_engines.Gcp method*), 208
- read_configuration() (*hvac.api.auth_methods.Github method*), 176

read_configuration() (hvac.api.auth_methods.Ldap method), 183
 read_configuration() (hvac.api.auth_methods.Mfa method), 186
 read_configuration() (hvac.api.auth_methods.Radius method), 191
 read_configuration() (hvac.api.secrets_engines.KvV2 method), 225
 read_connection() (hvac.api.secrets_engines.Database method), 245
 read_crl() (hvac.api.secrets_engines.Pki method), 229
 read_crl_configuration() (hvac.api.secrets_engines.Pki method), 230
 read_duo_behavior_configuration() (hvac.api.auth_methods.Mfa method), 186
 read_entity() (hvac.api.secrets_engines.Identity method), 217
 read_entity_alias() (hvac.api.secrets_engines.Identity method), 217
 read_entity_by_name() (hvac.api.secrets_engines.Identity method), 217
 read_group() (hvac.api.auth_methods.Ldap method), 183
 read_group() (hvac.api.auth_methods.Okta method), 188
 read_group() (hvac.api.secrets_engines.Identity method), 217
 read_group_alias() (hvac.api.secrets_engines.Identity method), 218
 read_group_by_name() (hvac.api.secrets_engines.Identity method), 218
 read_health_status() (hvac.api.system_backend.Health method), 251
 read_identity_integration() (hvac.api.auth_methods.Aws method), 199
 read_identity_whitelist() (hvac.api.auth_methods.Aws method), 199
 read_identity_whitelist_tidy() (hvac.api.auth_methods.Aws method), 199
 read_init_status() (hvac.api.system_backend.Init method), 252
 read_key() (hvac.api.secrets_engines.Transit method), 239
 read_leader_status() (hvac.api.system_backend.Leader method), 256
 read_lease() (hvac.api.system_backend.Lease method), 256
 read_lease() (hvac.v1.Client method), 148
 read_lease_config() (hvac.api.secrets_engines.Aws method), 203
 read_mount_configuration() (hvac.api.system_backend.Mount method), 259
 read_policy() (hvac.api.system_backend.Policy method), 261
 read_rekey_progress() (hvac.api.system_backend.Key method), 254
 read_role() (hvac.api.auth_methods.Aws method), 199
 read_role() (hvac.api.auth_methods.Azure method), 171
 read_role() (hvac.api.auth_methods.Gcp method), 175
 read_role() (hvac.api.auth_methods.Kubernetes method), 179
 read_role() (hvac.api.secrets_engines.ActiveDirectory method), 210
 read_role() (hvac.api.secrets_engines.Aws method), 203
 read_role() (hvac.api.secrets_engines.Database method), 245
 read_role() (hvac.api.secrets_engines.Pki method), 230
 read_role() (hvac.api.secrets_engines.RabbitMQ method), 247
 read_role_tag_blacklist() (hvac.api.auth_methods.Aws method), 199
 read_role_tag_blacklist_tidy() (hvac.api.auth_methods.Aws method), 199
 read_roleset() (hvac.api.secrets_engines.Gcp method), 208
 read_root_generation_progress() (hvac.api.system_backend.Key method), 254
 read_seal_status() (hvac.api.system_backend.Seal method), 262
 read_secret() (hvac.api.secrets_engines.KvV1 method), 222
 read_secret_metadata() (hvac.api.secrets_engines.KvV2 method), 225
 read_secret_version() (hvac.api.secrets_engines.KvV2 method), 225
 read_sts_role() (hvac.api.auth_methods.Aws

- method*), 199
 read_team_mapping() (*hvac.api.auth_methods.Github method*), 177
 read_urls() (*hvac.api.secrets_engines.Pki method*), 230
 read_user() (*hvac.api.auth_methods.Ldap method*), 183
 read_user() (*hvac.api.auth_methods.Okta method*), 189
 read_user() (*hvac.api.auth_methods.Radius method*), 191
 read_user() (*hvac.api.auth_methods.Userpass method*), 184
 read_user_mapping() (*hvac.api.auth_methods.Github method*), 177
 read_userpass() (*hvac.v1.Client method*), 148
 register_group() (*hvac.api.auth_methods.Okta method*), 189
 register_user() (*hvac.api.auth_methods.Okta method*), 189
 register_user() (*hvac.api.auth_methods.Radius method*), 191
 rekey() (*hvac.api.system_backend.Key method*), 254
 rekey() (*hvac.v1.Client method*), 148
 rekey_multi() (*hvac.api.system_backend.Key method*), 254
 rekey_multi() (*hvac.v1.Client method*), 149
 rekey_status (*hvac.v1.Client attribute*), 149
 remount_secret_backend() (*hvac.v1.Client method*), 149
 remove_nones() (*in module hvac.utils*), 265
 renew_lease() (*hvac.api.system_backend.Lease method*), 257
 renew_secret() (*hvac.v1.Client method*), 149
 renew_token() (*hvac.v1.Client method*), 149
 Request (*in module hvac.adapters*), 271
 request() (*hvac.adapters.Adapter method*), 269
 request() (*hvac.adapters.JSONAdapter method*), 270
 request() (*hvac.adapters.RawAdapter method*), 270
 reset_connection() (*hvac.api.secrets_engines.Database method*), 245
 restore_key() (*hvac.api.secrets_engines.Transit method*), 239
 retrieve_mount_option() (*hvac.api.system_backend.Mount method*), 259
 revoke_certificate() (*hvac.api.secrets_engines.Pki method*), 230
 revoke_force() (*hvac.api.system_backend.Lease method*), 257
 revoke_lease() (*hvac.api.system_backend.Lease method*), 257
 revoke_prefix() (*hvac.api.system_backend.Lease method*), 257
 revoke_secret() (*hvac.v1.Client method*), 150
 revoke_secret_prefix() (*hvac.v1.Client method*), 150
 revoke_self_token() (*hvac.v1.Client method*), 150
 revoke_token() (*hvac.v1.Client method*), 150
 revoke_token_prefix() (*hvac.v1.Client method*), 151
 rewrap_data() (*hvac.api.secrets_engines.Transit method*), 239
 rotate() (*hvac.v1.Client method*), 151
 rotate_crl() (*hvac.api.secrets_engines.Pki method*), 231
 rotate_encryption_key() (*hvac.api.system_backend.Key method*), 255
 rotate_key() (*hvac.api.secrets_engines.Transit method*), 240
 rotate_roleaset_account() (*hvac.api.secrets_engines.Gcp method*), 208
 rotate_roleaset_account_key() (*hvac.api.secrets_engines.Gcp method*), 209
 rotate_root_credentials() (*hvac.api.secrets_engines.Database method*), 245
 rotate_root_iam_credentials() (*hvac.api.secrets_engines.Aws method*), 204
- ## S
- Seal (*class in hvac.api.system_backend*), 261
 seal() (*hvac.api.system_backend.Seal method*), 262
 seal() (*hvac.v1.Client method*), 151
 seal_status (*hvac.v1.Client attribute*), 151
 secrets (*hvac.v1.Client attribute*), 151
 SecretsEngines (*class in hvac.api*), 166
 SecretsEngines (*class in hvac.api.secrets_engines*), 243
 session (*hvac.v1.Client attribute*), 151
 set_crl_configuration() (*hvac.api.secrets_engines.Pki method*), 231
 set_policy() (*hvac.v1.Client method*), 151
 set_role_id() (*hvac.v1.Client method*), 152
 set_signed_intermediate() (*hvac.api.secrets_engines.Pki method*), 231
 set_urls() (*hvac.api.secrets_engines.Pki method*), 231
 sign_certificate() (*hvac.api.secrets_engines.Pki method*), 232

sign_data() (*hvac.api.secrets_engines.Transit method*), 240
sign_intermediate() (*hvac.api.secrets_engines.Pki method*), 232
sign_self_issued() (*hvac.api.secrets_engines.Pki method*), 232
sign_verbatim() (*hvac.api.secrets_engines.Pki method*), 233
SigV4Auth (*class in hvac.aws_utils*), 266
start_generate_root() (*hvac.v1.Client method*), 152
start_rekey() (*hvac.api.system_backend.Key method*), 255
start_rekey() (*hvac.v1.Client method*), 152
start_root_token_generation() (*hvac.api.system_backend.Key method*), 256
submit_ca_information() (*hvac.api.secrets_engines.Pki method*), 233
submit_unseal_key() (*hvac.api.system_backend.Seal method*), 262
submit_unseal_keys() (*hvac.api.system_backend.Seal method*), 262
sys (*hvac.v1.Client attribute*), 153
SystemBackend (*class in hvac.api*), 167
SystemBackend (*class in hvac.api.system_backend*), 263
SystemBackendMixin (*class in hvac.api.system_backend*), 263

T

tidy() (*hvac.api.secrets_engines.Pki method*), 233
tidy_blacklist_tags() (*hvac.api.auth_methods.Aws method*), 200
tidy_identity_whitelist_entries() (*hvac.api.auth_methods.Aws method*), 200
token (*hvac.v1.Client attribute*), 153
token_role() (*hvac.v1.Client method*), 153
Transit (*class in hvac.api.secrets_engines*), 233
transit_create_key() (*hvac.v1.Client method*), 153
transit_decrypt_data() (*hvac.v1.Client method*), 154
transit_delete_key() (*hvac.v1.Client method*), 155
transit_encrypt_data() (*hvac.v1.Client method*), 155
transit_export_key() (*hvac.v1.Client method*), 156
transit_generate_data_key() (*hvac.v1.Client method*), 157
transit_generate_hmac() (*hvac.v1.Client method*), 157
transit_generate_rand_bytes() (*hvac.v1.Client method*), 158
transit_hash_data() (*hvac.v1.Client method*), 158
transit_list_keys() (*hvac.v1.Client method*), 158
transit_read_key() (*hvac.v1.Client method*), 159
transit_rewrap_data() (*hvac.v1.Client method*), 159
transit_rotate_key() (*hvac.v1.Client method*), 160
transit_sign_data() (*hvac.v1.Client method*), 160
transit_update_key() (*hvac.v1.Client method*), 161
transit_verify_signed_data() (*hvac.v1.Client method*), 162
trim_key() (*hvac.api.secrets_engines.Transit method*), 241
tune_auth_backend() (*hvac.v1.Client method*), 162
tune_auth_method() (*hvac.api.system_backend.Auth method*), 250
tune_mount_configuration() (*hvac.api.system_backend.Mount method*), 259
tune_secret_backend() (*hvac.v1.Client method*), 163

U

Unauthorized, 271
undelete_secret_versions() (*hvac.api.secrets_engines.KvV2 method*), 225
 UnexpectedError, 271
unimplemented_classes (*hvac.api.auth_methods.AuthMethods attribute*), 168
unimplemented_classes (*hvac.api.AuthMethods attribute*), 166
unimplemented_classes (*hvac.api.secrets_engines.SecretsEngines attribute*), 243
unimplemented_classes (*hvac.api.SecretsEngines attribute*), 167
unimplemented_classes (*hvac.api.system_backend.SystemBackend attribute*), 263
unimplemented_classes (*hvac.api.SystemBackend attribute*), 167

unimplemented_classes
 (*hvac.api.VaultApiCategory* attribute), 168
 unseal() (*hvac.v1.Client* method), 164
 unseal_multi() (*hvac.v1.Client* method), 164
 unseal_reset() (*hvac.v1.Client* method), 165
 unwrap() (*hvac.api.system_backend.Wrapping*
 method), 263
 unwrap() (*hvac.v1.Client* method), 165
 update_entity() (*hvac.api.secrets_engines.Identity*
 method), 218
 update_entity_alias()
 (*hvac.api.secrets_engines.Identity* method),
 219
 update_group() (*hvac.api.secrets_engines.Identity*
 method), 219
 update_group_alias()
 (*hvac.api.secrets_engines.Identity* method),
 219
 update_key_configuration()
 (*hvac.api.secrets_engines.Transit* method),
 242
 update_metadata()
 (*hvac.api.secrets_engines.KvV2* method),
 226
 update_password_on_user()
 (*hvac.api.auth_methods.Userpass* method),
 185
 update_userpass_password() (*hvac.v1.Client*
 method), 165
 update_userpass_policies() (*hvac.v1.Client*
 method), 166
 url (*hvac.v1.Client* attribute), 166
 urljoin() (*hvac.adapters.Adapter* static method), 269
 urljoin() (*hvac.v1.Client* static method), 166
 Userpass (class in *hvac.api.auth_methods*), 183

V

v1 (*hvac.api.secrets_engines.Kv* attribute), 221
 v2 (*hvac.api.secrets_engines.Kv* attribute), 221
 validate_list_of_strings_param() (in mod-
 ule *hvac.utils*), 265
 validate_member_id_params_for_group_type()
 (*hvac.api.secrets_engines.Identity* static
 method), 220
 validate_pem_format() (in module *hvac.utils*),
 266
 VaultApiBase (class in *hvac.api*), 167
 VaultApiCategory (class in *hvac.api*), 167
 VaultDown, 271
 VaultError, 271
 VaultNotInitialized, 271
 verify_signed_data()
 (*hvac.api.secrets_engines.Transit* method),
 242

W

Wrapping (class in *hvac.api.system_backend*), 263
 write() (*hvac.v1.Client* method), 166